

# HP Trust Center Connection Manager Administrators' Guide

Issue 24.03.0

© Copyright 2016, 2017 HP Development Company, L.P.

Confidential computer software. Valid license from HP required for possession, use or copying. Consistent with FAR 12.211 and 12.212, Commercial Computer Software, Computer Software Documentation, and Technical Data for Commercial Items are licensed to the U.S. Government under vendor's standard commercial license.

The information contained herein is subject to change without notice. The only warranties for HP products and services are set forth in the express warranty statements accompanying such products and services. Nothing herein should be construed as constituting an additional warranty. HP shall not be liable for technical or editorial errors or omissions contained herein.

First Edition: May 2024



# Contents

1	Device Management Software Introduction				
2	System Configuration and Precautions	6			
	Table 1 Required TCP/UDP ports for DMS	7			
3	Features	7			
	3.1 Multi-Language	7			
	3.2 Login	8			
	3.2.1 Session Timeout	10			
	Figure 5 Database connection error - login screen	.11			
	Figure 6 Database connection error - configuration screen	12			
	3.3 Initialize Settings	13			
	Figure 8 DMS initialize setting screen - 2	13			
	3.4 Overview	16			
	3.5 Device	20			
	(1) Add Group	25			
	(2) Add Sub Group	29			
	(4) Edit Group	33			
	(8) Delete Group	47			
	Table 2 Device status and active commands	50			
	(2) Send Command to Device	67			
	3.5.3 Support	73			



	3.6 Profile	79
	(1) Add Device Profile	82
	(3) Edit Device Profile	102
	(4) Delete Device Profile	119
	(3) Edit Connection Profile	145
	(4) Delete Connection Profile	147
	3.7 Task	173
	Table 3 Task status and marking	176
	3.7.1. Add Task	176
	3.7.4. Delete Task	199
	3.8 History	201
	3.8.2. Supported Export File Formats	206
	Figure 140 Export history file format - PDF	206
	3.9 Settings	208
	3.9.1. File	209
	A. Add BIOS/SW	210
	(1) Directory Service	233
	(2) Database	241
	(3) File Store Area	243
	3.10 Custom Design Portal	248
	3.11 Manage Trusted Zero Client	251
	3.11.3. Add Connection Profile	271
4	Troubleshooting	275



4.1 Connection Issues	275
4.2 Error Massages and Logs	275
4.3 Collect DMS Logs	276
4.4 Security Issues	277
4.5 Backup and Recovery	278



#### 1 Software Introduction

This Device Management Software (DMS) is a thin client and zero client management console tool which lets administrators centrally manage and deploy your client devices. The software lets you:

- Ensure secured HTTPS-based information transmission and communication with client devices
- Remotely update client device firmware/BIOS/OS, reset devices and upload firmware/BIOS/OS files
- Manage virtual desktop connection settings
- Manage administrator settings and identification
- Control real-time state of client devices and view status information
- Configure a schedule of power management, profile update, and firmware update
- Support remote connection with thin clients using VNC and SSH
- Manage and configure Anyware Trusted Zero Clients

#### 2 System Configuration and Precautions

The software provides IT administrators with a browser-based console for managing client devices. It supports browsers Google Chrome, Microsoft Edge, and Firefox. To get a better web page user experience, we recommend setting your display at a resolution of 1440x900 or above.

TCP and UDP ports assigned for the software are shown in the table below:

Port	Port Number	Description
TCP	20	FTP (Default communication port)
TCP	21	FTP (Control port)
ТСР	22	<ul> <li>SFTP (Secure File Transfer Protocol)</li> <li>SSH connection (remotely connect to devices)</li> </ul>
Copyright© 2024 HP Inc. 6		



UDP	69	TFTP (Trivial File Transfer Protocol)
TCP, UDP	389	LDAP
TCP	443	HTTPS port for browser to connect to DMS (Browser -> DMS)
UDP	1900	Microsoft SSDP Enables discovery of UPnP devices
TCP	3306	MySQL database system
TCP	5900	VNC connection (remotely connect to devices)
ТСР	6080	VNC web version remote connection package NoVNC:  DMS -> NoVNC (6080) -> Devices (VNC:5900)
ТСР	8443	HTTPS port between DMS and devices with latest LvOS releases: DMS (8443) <-> Device (8443)
ТСР	9080	SSH web version remote connection package GateOne:  DMS -> GateOne (9080) -> Devices (SSH:22)

Table 1 Required TCP/UDP ports for DMS

**Note:** For successful network connectivity, ensure that the required ports mentioned above are enabled.

#### 3 Features

# 3.1 Multi-Language

DMS supports user interface in English, Japanese, Korean, German, Traditional Chinese, and Simplified Chinese. It automatically switches language shown based on the browser language that the administrator uses. If it detects the administrator is using a Japanese browser, DMS will display the configuration pages in Japanese; if it isn't in the supported language listed above, it shows pages in English. If you want to change the language, select from the "Language" menu in the upper right corner of the overview page. It will show your selected language the next time you log in.

This guide demonstrates configuration pages in English. The following indicates English login screen:






Figure 1 English login screen

# 3.2 Login

There are two types of DMS administrators with different log-in authentication: an Admin (administrator) who can **View**, **Add**, **Edit**, **Delete** data; and a Viewer who is allowed to **View** information only.

New administrators can be added through the software or imported from LDAP (Lightweight Directory Access Protocol) system. The same user account is allowed to login simultaneously from different locations.






Figure 2 Login screen

Open a web browser and then enter the IP address of the DMS server. (https://<IP address>/DMSWeb/index.html). You will see the log-in screen of the DMS front page.

When you first log in DMS, the default administrator username is "administrator" and the password is "administrator". For security purposes, you will be asked to do initialize settings, including adding an administrator account to replace the default account. You can reconfigure the account and password in **Settings** ->

#### Administrator.

If the administrator account is imported from LDAP, use LDAP username and password to log in DMS. DMS will compare and authenticate LDAP user information.

Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.



# 3.2.1 Session Timeout




Figure 3 DMS session timeout message

If no activity occurs during the timeout period of 30 minutes, the DMS session times out and it will automatically return to the login screen and display the reason for returning to the login page.



## 3.2.2 Database Connection Error



Figure 4 Database connection error screen

If DMS cannot make a successful connection with the database server, an error message appears. Click **OK** and follow the instructions to fix connection issues.




Figure 5  $_{
m Database\,connection\,error\,-\,login\,screen}$ 

Enter your administrator account/password and press Sign in to login.






Figure 6 Database connection error – configuration screen

After identifying and solving the problem that causes the database access failure, enter the identified domain name or IP address of the databased host server. Click **Finish** to reconfigure the database or click **Reset** to erase the data on the page.



# 3.3 Initialize Settings

When an administrator first login DMS, you have to configure some initial settings, including: assign server name or IP address, and add an administrator username and password.



Figure 7 DMS initialize setting screen - 1

Use the default administrator username and password to log in DMS. You will see the welcome to DMS screen. Press **OK** to enter the initialize setting screen.



Figure 8 DMS initialize setting screen - 2

This page lets you configure host domain name or IP address. Enter DMS domain name or IP address that is present on the network. You can configure a virtual host deployed in the network and get the IP address through DHCP or a static IP. If there is a chance of changing the host IP address in the future, it is recommended to set the network of the virtual host as the domain name.

Press **Next** to enter the next setting page, or press **Reset** to erase the data on the page.





Figure 9 DMS initialize setting screen - 3

Add an administrator username and password on the page. **Note** that you have to choose a different administrator name from the default name when you create a new account. Enter your new username, password and re-confirm the password. Press **Finish** to complete DMS initialize settings.

To secure the DMS, it is critical for administrators to remember administrator's account and password. If there is only one user with the privilege of having Admin access, there is no way to regain or recover access to his/her account after forgetting his/her account and password. It is recommended to establish at least 2 users with Admin access privilege.

Press Reset to erase the data on the page.




Figure 10 DMS initialize setting screen - 4



After assigning server name or IP address, and adding the administrator username and password successfully, you will see the log out screen. Press **OK** to log out DMS. You have to use the new username and password the next time you log in DMS.



#### 3.4 Overview

After you log in DMS, the Overview home webpage appears. The Overview page shows device type, device status, task execution status, task warning / failed log, server status, and online users information.




Figure 11 Overview home page

There are a few sections that are included on the Overview homepage. In the upper-right corner of the screen, it shows the administrator's name. Click the to find copyright and



and software information; press **Sign Out** to log out DMS; or press **Language** to select the display language of the web page.

DMS feature list is shown in the left side of the screen. You can choose

Overview Overview, Device Device, Profile Profile, Task Task, History History, and Settings

to configure these features.

In the upper left side of the screen, it shows the last data synchronized time, e.g. Last Updated Time: 2018.01.23 . AM 09:58 . Click the icon to refresh



data. If the last updated time is within 60 seconds of the moment, it shows **Just sync**. Next to the last updated time is the server status, e.g.

Server Status Health . Click the icon to show detailed server used space information. And the last is the number of online users Online Users 8 . Click the icon to show online user information.

If the server operates normally, the server status shows **Healthy** 

Server Status: Healthy . If the hard drive usage rate or device files used space goes beyond 90%, the server status shows **Warning**Server Status: Warning .

After the connection between DMS and Anyware Trust Center is successfully set up, the current status of the Trust Center (Healthy

Trust Center: Unhealthy

/Unhealthy ) will be displayed on the left side of the online users. If you haven't configure the Trust Center, it will display Unset


Trust Center: Unset . Click the icon to configure the Trust Center. You can add or modify the connection settings.



There are two sections that are included in the central screen. **Device Type** on the left summarizes device type information, including total device number and the number of each device type. Click a device type in the list (e.g. 29B8C00) and a pie chart on the left will show the percentage and number of the device type. **Device Status** on the right shows device status earlier on the same day, including devices in offline, online, factory reset, SW update, reboot, connected, sleep, and BIOS update states. Next to each state is the number of the state being executed, added once every hour.

Select a specific period of time in **Device Status** to show the number of devices that match the device status at that particular time. The default period displayed is the status when you move to the Overview page.





In the lower part of the screen, the screen is divided into two parts. **Task Execution Status** on the left shows the task execution results and the success rate. It also summarizes the status of all the current tasks, including Incoming, In Progressing, Overdue, Executed, and Failed. **Task Warning/Failed Log** on the right shows all **Warning** and **Fail** execution events happening earlier on the same day.

Move the mouse to a specific execution success bar in **Task Execution Status** to show the number of success and fail results.



Click **Task Execution Status** title to show task screen and view all task information. Click **Task Warning/Failed Log** title to show history screen and view all DMS event history, including add/edit/delete events and all task execution results.







Figure 12 View online users

Click the icon in online users to show online administrator and viewer information, including user ID, access level, online date and time. The list defaults to the descending order of "Online Time", and the last online user will be displayed first. In search field, you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click each column header to sort the data in ascending or descending order.





Click **CANCEL** or icon to close the dialogue and return to Overview page.




Figure 13 About screen

In the upper right of the screen, it shows the user name. Click the drop down icon and click About option to show copyright and software information, including DMS software version, copyright disclosure statement, and installed packages that DMS uses.

#### 3.5 Device

The Device page provides connected device information. It lets you view device information, configure the group or ungroup to facilitate device management, power on/off or reboot devices for a specific or multiple groups, update devices for a specific or multiple groups, reset hardware for a specific or multiple groups, and update connection profile or device profile configuration.


Also, the **Device/Support** page shows online and VNC/SSH-supported devices. Administrators can use VNC or SSH session to control and manage the remote desktop, and furthermore clarify preliminary issues and fix problems for the connected devices.

When DMS is initially started, there isn't any default group being created. It is recommended to create a group when you start to use the software. When a device turns on and is registered to DMS, you will find the ungrouped device in **Device** -> **Ungrouped**Copyright© 2024 HP Inc. 20



page. Then you can assign the device to a selected group, according to its characteristic, for your further management. You can only perform remotely power on/off and reboot commands on an ungrouped device. For a grouped device, you can remotely perform power on/off, reboot, factory reset, SW update, connection profile update, device profile update, and

BIOS update activities through the DMS.



# 3.5.1 Grouped

Figure 14 Grouped Device

Click **Device** in the left side of the screen. You will see information of the created device groups, including group name, device type, device profile, connection profile, device



number, and the last edited time. The list defaults to the descending order of "last edited time", and the last edited item will be displayed first.

Select a group that you want to view detailed information of its devices. You are able to send power on/off, reboot, device update, factory reset, connection profile or device profile configuration update commands to the devices in a specific group.

You can add or delete devices from a group, move devices to a new group, or send power on/off, reboot, device update, factory reset, connection profile or device profile update commands to a specific device or multiple devices.


If there is a scheduled task being executed in the group, an icon will be displayed on the left, and when the mouse is moved to the top, a prompt message "Task is running" will be displayed.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria (e.g. Device Type, Group, Device Profile, Connection Profile, MAC Address, IP, SN, SW Version, BIOS Version and Status) to find particular data in grouped device screen. After choosing the criteria you want to use and entering your search words, click the add rule icon

add rule in search list. You can add one or several search criteria. After completing the setting, click **SEARCH** to start data searching; or click **CANCEL** to close search screen and go back to grouped device screen.





Click the import icon in the toolbar to import previously exported group data. Click the export icon in the toolbar to export group data. If you didn't click and choose any group from the list, it exports all group data; if you click and choose a specific group from the list, it only exports the selected group data.

Click the export device inventory report icon in the toolbar to export device inventory information. This will export information of all devices in the group.

Click the expand icon in the toolbar to extend and show all groups and the device information within each group. Click the collapse icon in the toolbar to collapse all groups and the device information within each group.

Click each column header to sort the data in order of letter or number.




Choose a group from the list and click a toolbar icon at the top of the window
 to edit, send commands, view, or delete a group.



- Click the edit icon in the toolbar to edit group information or configure device name.
- Click the send command icon in the toolbar to send commands to devices in a group.
- Click the view icon in the toolbar to view group information.
- Click the delete icon in the toolbar to delete a group.

Right-click a group from the list and it will show a shortcut list of sending commands, editing, viewing, deleting, exporting and importing, which are the same as the icons in the toolbar.



- Choose a device in a group and click a toolbar icon at the top of the window to rename device, send command, view, move the device to another group, or ungroup the device from the group.
- Click the rename device icon in the toolbar to configure device name.
- Click the send command icon in the toolbar to send commands to a selected device.
- Click the view icon in the toolbar or click the left mouse button twice to view device information.
- Click the move device icon in the toolbar to move a selected device to another group.
- Click the ungroup icon in the toolbar to remove a selected device from the current group. The removed device will be displayed in **Ungrouped** page.



Right-click a device from the list and it will show a shortcut list of renaming device, sending commands, viewing device information, moving to another group, and ungrouping, which are the same as the icons in the toolbar.



You can choose one or more groups or devices at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and device states.

### (1) Add Group

Before adding a group, ensure Device Type, Device Profile and Connection Profile data has been created and configured in DMS.

When a client device is registered to DMS server, it will upload device type it belongs to. You don't need to manually add the device type. If there isn't any device being registered in DMS, a message *No Device exist*, appears when adding a group.

Device Profile and Connection Profile can be created and configured in Profile > Device Profile and Profile -> Connection Profile.






Figure 15 Add Group - Info


Click the **ADD** icon in Grouped page to create a new group. Click **Info** tab on the left to enter the group name and choose device type, device profile, and connection profile. You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. If a device type has been established and existed in DMS, it will be displayed in the field in sequence. The device profiles and connection profiles available for this device type will also be displayed.

- Group: You must configure the group name. The length of the name field is 1 to
   20 characters. Space is not allowed in group name.
- Device Type: Select a device type from the drop-down list. This field must be filled in. The drop-down list is generated when a device is registered to the DMS server or the model name passed through Anyware Trust Center.



- Device Profile: Select a device profile from the drop-down list. This field must be configured. The device profile must be created first in Profile -> Device
   Profile page.
- Connection Profile: Select a connection profile from the drop-down list. This field must be filled in. The connection profile must be created first in **Profile** -> Connection Profile page. If the devices in the group want to apply their own settings, select "Set From Device". If DMS and the Trust Center are successfully configured and connected, the Trusted Zero Clients will be applied with default values. After selecting the Device Profile and Connection Profile you would like to apply, all devices under the group will be set to default values based on the profile configurations.



- Click Next > or the Device tab on the left to move to the next setting page.
- Click ADD to add the new group and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Reset Form to reset the page content back to the default state and back to the first Add Group page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 16 Add Group - Device

Click **Device** tab on the left to select devices belonging to the device type to this group. All ungrouped and grouped devices will be displayed in the list. You can select one or multiple devices from the list.

You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click ADD to add the new group and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content
   Copyright© 2024 HP Inc.



back to the default state and back to the first Add Group page.

• Click **CANCEL** to restore your previous settings and leave the page.

## (2) Add Sub Group

A subgroup refers to a subset in a group, and the subset itself also constitutes a group.

You can only create one level of subgroups under a parent group.




Figure 17 Add Sub Group - Info


Click the **ADD SUB GROUP** icon in Grouped page to create a new subgroup. Click **Info** tab on the left to enter the subgroup name and choose device profile and connection profile. You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. The device type cannot be edited, and its type is inherited from the parent group. Subgroups can choose a Device Profile or Connection Profile different from the parent group, and the selection will not be affected by the changes of the parent group. The default is the value of the parent group.



- Sub Group Name: You must configure the subgroup name. The length of the name field is 1 to 20 characters. Space is not allowed in subgroup name.
- Device Type: This cannot be edited. The type is inherited from the parent group.
- Device Profile: Select a device profile from the drop-down list. This field must be filled in. The device profile can be created in Profile -> Device Profile page.
- Connection Profile: Select a connection profile from the drop-down list.
   This field must be configured. The connection profile can be created in Profile Connection Profile page. If the devices in the group want to apply their own settings, select "Set From Device".

If DMS and the Trust Center are successfully configured and connected, the Trusted Zero Clients will be applied with default values. After selecting the Device Profile and Connection Profile you would like to apply, all devices under the subgroup will be set to default values based on the profile configurations.



- Click Next > or the Device tab on the left to move to the next setting page.
- Click ADD to add the new subgroup and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content
   back to the default state and back to the first Add Sub Group page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 18 Add Sub Group - Device

Click **Device** tab on the left to select devices belonging to the device type to this group. All ungrouped and grouped devices will be displayed in the list. You can select one or multiple devices from the list.

You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click ADD to add the new subgroup and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content
   Copyright© 2024 HP Inc.
   31



back to the default state and back to the first Add Sub Group page.

• Click **CANCEL** to restore your previous settings and leave the page.

# (3) Add Device




Figure 19 Add devices to parent or sub group

Click the ADD DEVICE icon in Grouped page to place devices to a parent group or a subgroup. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

- Please first select the parent group or subgroup you want to put the devices into, and then select the devices you want to put into it.
- Group: Select a parent group or its subgroup from the drop-down list.
   This field must be filled in. The default is the parent group.

Copyright© 2024 HP Inc.



- The device list includes ungrouped or grouped devices. Devices can be single or multiple-selected to add into the group.
- Click ADD to add the devices in a parent group or a subgroup and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and back to the first Add Device page.
- Click **CANCEL** to restore your previous settings and leave the page.

#### (4) Edit Group

You can only edit a group which isn't performing any task. After changing Device Profile or Connection Profile in Edit Group window, it will display the new task in Task window.

Performing the task will apply the changed settings to all devices that are included in the group.




Figure 20 Edit Group - Info


Choose a group from the list and click the edit icon in the toolbar to show edit group configuration window. You can also right-click a group from the list to show the edit option.



In the Info tab it includes settings of group name, device type, device profile and connection profile. The device type is read only and cannot be modified. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Group: You must configure the group name. The length of the name field is 1 to 20 characters. Space is not allowed in group name.
- Device Type: The field shows the selected device type and cannot be changed (i.e., is grayed out).
- Device Profile: Select a device profile from the drop-down list. This field must
   be filled in. The device profile can be created in Profile -> Device Profile page.
- Connection Profile: Select a connection profile from the drop-down list.

This field must be configured. The connection profile can be created in Profile -> Connection Profile page. If the devices in the group want to apply their own settings, select "Set From Device". If DMS and the Trust Center are successfully configured and connected, the Trusted Zero Clients will be applied with default values. After selecting the Device Profile and Connection Profile you would like to apply, all devices under the group will be set to default values based on the profile configurations.



- Click **Next >** or the **Device** tab on the left to move to the next setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.



- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 21 Edit Group - Device

The device window displays device name, MAC and IP address in the group. Only the device name can be edited, and the naming rules such as the character length are displayed at the bottom of the window.

You can only edit a device which is in online state and edit a group which isn't performing any task. When a device isn't managed by DMS, or when a device is managed by DMS but in ungrouped state, device naming can only be configured at device side. The updated name will be reported and synchronized to DMS in the next registration or periodic state update. Once the device is added in a group, device naming will be configured by DMS (Trusted Zero Client is not subject to this restriction), and the updated name will be reported and synchronized to the device.



- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to restore your previous settings and leave the page.




Figure 22 Task scheduling for an edited group

If a group is created with associated devices, after a group's **Device Profile** or **Connection Profile** being updated, DMS displays the new task in Task window. Performing the task will apply the changed settings to all devices that are included in the group.

You can execute the task within 5 minutes or in the future by specifying the date and time. The date can only be configured as Today or Tomorrow. Once you complete the setting, click the **Apply** button to save the changes and close the dialogue.

The new task will be displayed in the Task scheduling list with a name format of sTask\_G9999 (9999 is a randomly generated sequence number). A task of changing device profile or connection profile cannot be edited or deleted.



# (5) View Group




Figure 23 View Group - 1

Choose a group from the list and click the view icon in the toolbar to view group configuration information. You can also right-click a group from the list to show the **View** option.


The view group window displays group relating information, including group name, device type, device profile, connection profile, created time, and edited time.

If DMS and the Trust Center are successfully configured and connected, you can also view the

Device Profile and Connection Profile default values of the

Trusted Zero Clients.





Click **EDIT** to enter the edit group window or click **CLOSE** to leave the view window.

Click the **Delete Item** icon  $\Box$  Delete Item to delete the specific group item.




Figure 24 View Group - 2

If the viewed group is processing tasks, it will show This item is included in processing tasks.

You can only view the processing task details but cannot

edit or delete it. Copyright© 2024 HP Inc.



Click the CANCEL to leave the view window.

#### View Device Info Device Name Static amdx86-64 Reported Desired Device Type MAC Address Default Bilby 00:30:04:1B:54:2B IP Address 192.168.9.142 Base Board Serial Number SW Version SW Build Date 24.03.0-rc13 2024/03/26 BIOS Version BIOS Build Date N/A N/A CANCEL MOVE

#### (6) View Device

Figure 25 View Device Information (Grouped)

Choose a device from the list and click the view icon in the toolbar or click the left mouse button twice to view device information. You can also right-click a device from the list to show the **View** option.


When DMS and the Trust Center are successfully configured and connected, you can view static, reported, desired, and default setting details of the Trusted

#### Zero Clients.

Click **Info** or any tab on the left to switch the setting page at any time during the configuration process. The static, reported, desired, and default content is only displayed for specific device types.

When you click the menu of Static, Reported, Desired or Default on the left, you
can view the setting contents belonging to these different categories. Click the
tab above to switch between different setting items and their details.





- Click Move to show group selection window and move the device to the specific group.
- Click CLOSE or icon to leave the viewing page.



## (7) Edit Device




Figure 26 Edit Device

Choose a device from the list and click the edit icon in the toolbar to edit device information. You can also right-click a device from the list to show the **Edit** option.

The device window displays device name, MAC and IP address. Only the device name can be edited, and the naming rules such as the character length are displayed at the bottom of the window.

You can only edit a device which is in online state and edit a group which isn't performing any task. When a device isn't managed by DMS, or when a device is managed by DMS but in ungrouped state, device naming can only be configured at device side. The updated name will be reported and synchronized to DMS in the next registration or periodic state update. Once the device is added in a group, device naming will be configured by DMS, and the updated name will be reported and synchronized to the device.

- Click **SAVE** to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon
   Reset Form to reset the page content
   Copyright© 2024 HP Inc.



back to the unedited state.

Click CANCEL to restore your previous settings and leave the page.




Figure 27 Edit Trusted Zero Client Device - Info

When DMS and the Trust Center are successfully configured and connected, you can edit device name and other settings. You can click **Info** or other tabs to switch the setting page at any time during the process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In **Info** tab, it shows device name, device type, MAC and IP address, serial number, firmware version and build date, BIOS version and build date, hardware version, WiFi MAC address, SSL support and device status. Only the device name can be edited.

- Click Next > or the Display Setting tab on the left to move to the next setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Reset Form to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 28 Edit Trusted Zero Client Device – Display Setting

You can click **Display Setting** or other tabs to switch the setting page at any time during the process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In **Display Setting** tab, it shows the settings related to the monitor(s) currently connected to the Trusted Zero Client. You can configure the display position, resolution, rotation, and set the main display.

- Position: Displays the position of the monitor(s) currently connected to the Trusted Zero Client. After selecting the monitor to be adjusted
   (blue box), you can drag the mouse to adjust its position.
- Resolution: Configure the resolution of the selected monitor (blue box) from the drop-down menu. Once changed, the upper screen will resize with the settings.
- Rotation: Select Standard, 90°, 180° or 270° from the drop-down menu to set the
  direction for the selected monitor (blue box). Once changed, the upper screen
  will adjust its orientation according to the settings.
- Main Screen: Select a display model currently connected to Trusted
   Copyright© 2024 HP Inc.



Zero Client from the drop-down menu to set the main display.

- Click Next > or the Sound Setting tab on the left to move to the next setting page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click **SAVE** to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Reset Form to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 29 Edit Trusted Zero Client Device - Sound Setting

You can click **Sound Setting** or other tabs to switch the setting page at any time during the process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.



In Sound Setting tab, it shows the settings related to the audio device(s) currently connected to the Trusted Zero Client. You can configure the audio output and input settings.

- Output: Select an audio output device currently connected to Trusted Zero Client from the drop-down menu.
- Input: Select an audio input device currently connected to Trusted Zero Client from the drop-down menu.
- Click **Next >** or the **Support Bundle** tab on the left to move to the next setting page.
- Click < Previous or the Display Setting tab on the left to move back to the previous setting page.
- Click **SAVE** to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the **Reset Form** icon Reset Form to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.



Figure 30 Edit Trusted Zero Client Device – Support Bundle



You can click **Support Bundle** or other tabs to switch the setting page at any time during the process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The Support Bundle is a record of diagnostic and troubleshooting messages generated by the device. Administrators can use the information to diagnose and fix problems. The records can be generated automatically or manually after the administrator send a command.

When you click Support Bundle on the left, it lists all the log files on the device, which can be sorted by descending or ascending order according to the recording time or file size.

Click the RETREVE icon to send a command to the device to generate a log file.

After success, a new data will be added to the list. After clicking the data in the list, the selected item will be displayed in reverse color. You can click (Export) or (Delete) to export the file to another location or delete the log file. Only one item can be selected at a time.

- Click < Previous or the Sound Setting tab on the left to move back to the previous setting page.
- Click **SAVE** to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Reset Form to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.



#### (8) Delete Group

You can only delete a group if there are no processing tasks or commands for the group or the devices in the group. When there is a processing task or command, the delete group command is not active and you can only view the group information.






Figure 31 Delete Group

Choose a group from the list and click the delete icon in the toolbar to delete the specific group. You can also right-click a group from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** or icon to leave the window without changes or click **Delete** to confirm the deletion.







(9) Send Command

Figure 32 Send command through toolbar




Figure 33 Send command through shortcut list

Choose a group from the list and click the send command icon in the toolbar to send commands to all devices in the group.

You can also right-click a group from the list to show the **Send Command** option.



You can choose one or many groups to send a command. When devices are processing a task, the send command is not active.

The commands SW Update or BIOS Update are displayed depending on whether the selected device type supports this feature.

Category	Device Status	Active Commands	Description
		Power off	
		Reboot	
		SW Update	
		BIOS Update	
		Factory Reset	
		Connection Profile Update	
		Device Profile Update	A user is using the devices or the device is in standby
	Online	Rename	state.
			The network would be disconnected when a
	Sleep	N/A	device is in sleep state. You can only wake up the device from the endpoint side.
	Reboot	N/A	The device is rebooting.
	SW Update	N/A	The device is updating OS or firmware.
	BIOS Update	N/A	The device is updating BIOS.
	Factory Reset	N/A	The device is resetting hardware.
	Connected	N/A	The device is in Citrix, RDP or VMware session.
Grouped			
Device	Offline	Power on	The device is off, can't connect to network, or break down.
		Power off	
	Online	Reboot	A user is using the device or the device is in standby state.
			The network would be disconnected when a
	Sleep	N/A	device is in sleep state. You can only wake up the device from the endpoint side.
Ungrouped			
	Office -	Doweron	The device is off control connect to a trivial control to
Ungrouped Device		N/A Power on	The network would be disconnected when a device is in sleep state. You can only wake up the de



#### Table 2 Device status and active commands

The supported commands include power on/off, reboot, device update, factory reset, connection profile update, and device profile update. When devices are in some status, a command may not be active. Please refer to table above for more device type and active command details.

The **SW Update** or **BIOS Update** command sent to devices will trigger the device update action and reboot the devices after completing update.




Figure 34 Send command – Select SW

When **SW Update** command is selected, it shows OS / firmware selection screen. The file list shows all available files and information associated with this device type, including file name and description.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.



The list is displayed in ascending order by default. Click the column header of to sort the data in order of letter or

Sort data in ascending order

▶ File Name
 OS\_29B8C00\_1.3.23\_20200811
 OS\_29B8C00\_1.3.34\_20200827
 OS\_29B8C00\_1.4.29\_20200621
 OS\_29B8C00\_1.4.63\_20200705
 ▶ File Name
 OS\_29B8C00\_1.5.79\_20200522
 OS\_29B8C00\_1.4.63\_20200705
 OS\_29B8C00\_1.4.63\_20200705
 OS\_29B8C00\_1.4.63\_20200705
 OS\_29B8C00\_1.4.29\_20200621

Sort data in descending order

You can only select one file for OS /


firmware

update and cannot choose multiple files. After choosing the file you would like to send update command, click **SEND** to execute update command and leave the file selection window.

Click **CANCEL** or icon to leave the file selection window without changes.

When DMS and the Trust Center are successfully configured and connected, the following screen displays Trusted Zero Client (such as "FS-FP5V" and "Bilby") information. The SW information is displayed in the list, including name, version and hash value of the registered device. By default, the list is sorted according to the descending version number, and the data with higher numbers

(9->0), letters (Z->A) or characters with more strokes will be displayed first.








Figure 35 Send command – Select BIOS

When **BIOS Update** command is selected, it shows BIOS selection screen. The file list shows all available files and information associated with this device type, including file name and description.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

The list is displayed in ascending order of file name by default. Click the column header of **File Name** to sort the data in order of letter or number.


Sort data in ascending order



Sort data in descending order

You can only select one file for BIOS cannot choose multiple files. After the file you would like to send update click **SEND** to execute update and leave the file selection window.

Click **CANCEL** or icon to leave the file window without changes.



# (10) Devices in Group




Figure 36 Grouped Devices

Choose a group from the list. Double-click left mouse button or click the icon on the left to  $\nabla$  and the group. Double-click left mouse button again or click the icon on the left to collapse the group.

Group content shows the details of devices in the group, including a device's name, MAC address, Endpoint ID, IP address, SW version, BIOS version, serial number, device state, and the last online time.

Click the add icon ADD SUB GROUP in an expanded group to add a new sub-



group in the group. Only the same type of devices can be added in a group. If there isn't a add icon in an expanded group for you to add new sub-groups, it indicates this group is processing a task and cannot be added new sub-groups for the moment.

Click the add icon in an expanded group to add a new device in the group or sub-group. Only the same type of devices can be added in a group. If there isn't a add icon in an expanded group for you to add new devices, it indicates this group is processing a task and cannot be added new devices for the moment.

Choose a device in a group and click a toolbar icon at the top of the window to view information, move the device to another group, or ungroup the device from the group.

- Click the view icon in the toolbar or click the left mouse button twice to view device information.
- Click the move device icon in the toolbar to move a selected device to another group.
- Click the ungroup icon in the toolbar to remove a selected device from the current group. The removed device will be displayed in

#### **Ungrouped** page.

Right-click a device from the list and it will show a shortcut list of viewing information, setting default value, moving to another group, and ungrouping, which is the same as the icons in the toolbar.



You can choose one or more groups or devices at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and device states.






Figure 37 Add Sub Group in a Group-Info


Click the ADD SUB GROUP icon in Grouped page to create a new subgroup. Click **Info** tab on the left to enter the subgroup name and choose device profile and connection profile. You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. The device type cannot be edited, and its type is inherited from the parent group. Subgroups can choose a Device Profile or Connection Profile different from the parent group, and the selection will not be affected by the changes of the parent group. The default is the value of the parent group.

- Sub Group Name: You must configure the subgroup name. The length of the name field is 1 to 20 characters. Space is not allowed in subgroup name.
- Device Type: This cannot be edited. The type is inherited from the parent group.
- Device Profile: Select a device profile from the drop-down list. This field must be filled in. The device profile must be created first in
   Profile -> Device Profile page.



Connection Profile: Select a connection profile from the drop-down list. This field must be configured. The connection profile must be created first in **Profile**-> **Connection Profile** page. If the devices in the group want to apply their own settings, select "Set From Device". If DMS and the Trust Center are successfully configured and connected, the Trusted Zero Clients will be applied with default values. After selecting the Device Profile and Connection Profile you would like to apply, all devices under the subgroup will be set to default values based on the profile configurations.



- Click **Next >** or the **Device** tab on the left to move to the next setting page.
- Click ADD to add the new subgroup and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Reset Form to reset the page content back to the default state and back to the first Add Sub Group page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 38 Add Sub Group in a Group - Device

Click **Device** tab on the left to select devices belonging to the device type to this group. All ungrouped and grouped devices will be displayed in the list. You can select one or multiple devices from the list.

You can click **Info** or **Device** tab to switch the setting page at any time during the process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click ADD to add the new subgroup and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon
   Reset Form to reset the page content
   Copyright© 2024 HP Inc.



back to the default state and back to the first Add Sub Group page.

Click CANCEL to restore your previous settings and leave the page.




Figure 39 Add Device in a Group

Click the add icon in an expanded group to add new devices in the group or sub-group. Only the same type of devices can be added in a group. First select the parent group or subgroup, and then select the devices to be placed in the group.


**Group** is a drop-down menu. It lists the parent groups and all subgroups below the parent group. The default is the parent group and the information is required. All ungrouped and grouped devices will be displayed in the list. You can select one or multiple devices from the list.

In search field, you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.



Choose one or many devices from the list and click **ADD** to add the devices and leave the page.

Click **CANCEL** or icon to restore your previous settings and leave the page.



# (11) Export Group

Figure 40 Export Group Confirmation Window

Choose one or multiple groups from the device group list to export the data. Click the export icon in the toolbar or click **Export** from the shortcut list to export group data. If you didn't click and choose any group from the list, it exports all group data; if you click and choose a specific group from the list, it exports the selected group data.

Click **EXPORT** to export group data. Depending on your browser setting, a window may appear for you to choose the export file location, or the file is exported directly to an assigned download location. If there is any error happening during exporting process, it shows error message.





# Click **CANCEL** or icon to leave the export window without changes.

[\*DMS\*] (\*Version\*\*; 2.2.0\*\*, Create Time\*\*\* 20180601092525\*), "device TypeData\*\* [\*Trems\*\*] (\*Trems\*\*] (\*Trems\*\*] (\*Trems\*\*] (\*Trems\*\*) (\*Trems\*\*), "availar type\*\*), "default/Value\*\* admin\*\*, "required\*\*1, "subFekerray\*\* (!], "colorformar\*\* (0, "way\*\*) (\*Trems\*\*), "availar type\*\*), "availar type\*\*, "availar ty "name": "HTTP", "value" (3), "name": "HTTPS", "value" (1), "mutualExclusion" (3), "field" (1), "content type" (3), "individue" (3), "almysopport (1), "bestypentwarde (3), value" (1), "mutualExclusion" (3), "field (1), "content type" (3), "individue" (3), "field (1), "mutualExclusion" (3), "

# Figure 41 Export Group Data

The exported data includes group information, and the device, device profile, and connection profile information in the group.

The exported format is a compressed file (.zip) with a file name

DMS Group yyyymmdd hhmmss.zip ("DMS Group": fixed characters, "yyyymmdd": exported year/month/day, "hhmmss": exported time - hour/minute/second). The compressed file includes text and image files.

The item or data is displayed with quotation marks (""). Two values are separated with a comma (","). If not specified otherwise, please do not change exported contents, so as to avoid any importing error.



# (12) Import Group




Figure 42 Import Group

In Group main window, click the import icon in the toolbar to import group data. You can drag the file here or click **Browse** and choose the file (\*.zip) you want to import. You can only import one file at a time.

Click **IMPORT** to import group data and then leave the window. If there is any error happening during importing process, it shows error message. You can download and view the error report.

Click **CANCEL** or icon to leave the import window without changes.



# (13) Export Device Inventory Report




Figure 43 Export Device Inventory Report - Grouped

Click the export icon in the toolbar to export device inventory report. This will export information of all devices in the grouped page. The exported format is a .csv file with a file name DeviceList\_yyyymmdd\_hhmmss.csv ("DMS\_DeviceList": fixed characters, "yyyymmdd": exported year/month/day, "hhmmss": exported time - hour/minute/second).

Depending on your browser setting, the inventory report would be exported to a default file download location, or you would be asked to select a file location to save the file. If the is an error happened in exporting process, an error message appears.



# 3.5.2 Ungrouped




Figure 44 Ungrouped Device

Click **Device** in the left side of the screen. Then click **Ungrouped** page to show all devices which are not included in any group.

The list shows all ungrouped device information, including each device's name, MAC address, endpoint ID, device type, IP address, SW version, device status, and the last online time. The list defaults to the descending order of "Online Time", and the last online device will be displayed first.

When a device turns on for the first time, it is automatically registered to DMS, which is located in the same network, and sends device information to DMS.


After completing the register, the device is shown in ungrouped page.

In search field, you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria to find particular data in ungrouped device screen.



After choosing the criteria (e.g. Device Type, MAC Address, IP, SN, SW Version, BIOS Version and Status) you want to use and entering your search words, click the add rule icon \_\_\_\_\_\_ to add rule in search list. You can add one or several search criteria. After completing the setting, click SEARCH to start data searching; or click CANCEL to close search screen.



Click the redistribute icon in the toolbar to redistribute device information.

Click the import icon in the toolbar to import device data.

Click the export device inventory report icon in the toolbar to export device inventory information. This will export information of all devices in Ungrouped.

Click each column header to sort the data in order of letter or number.



The default sorting order is according to the latest online time of a device.

Choose a device in the ungrouped page and click a toolbar icon at the top of the Copyright© 2024 HP Inc. 64



window to send commands, move the device to a specific group, set default properties, view device, or delete the device.

- Click the send commands icon in the toolbar to send commands to a selected device.
- Click the move device icon in the toolbar to move a selected device to a specific group.
- Click the set default properties icon in the toolbar to configure one or multiple devices' default values in a group.
- Click the view icon in the toolbar or click the left mouse button twice to view device information.
- Click the delete icon in the toolbar to delete the device. **Note** that only an offline device can be deleted. When a deleted device is registered to DMS once again in the future, it will be shown in ungrouped list.

Right-click a device from the list and it will show a shortcut list of sending commands, moving to a specific group, setting default properties, viewing information, or deleting a device which is in offline state, which is the same as the icons in the toolbar.



You can choose one or more groups or devices at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and device states.



# (1) View Device




Figure 45 View Device (Ungrouped)


Choose a device from the list and click the view icon in the toolbar or click the left mouse button twice to view device configuration information. You can also right-click a device from the list to show the **View** option.

If DMS and the Trust Center are successfully configured and connected, you can view static, reported, desired, and default setting details of the Trusted Zero Clients.

Click **Info** or any tab on the left to switch the setting page at any time during the configuration process. The static, reported, desired, and default content is only displayed for specific device types.

When you click the menu of Static, Reported, Desired or Default on the left, you can view the setting contents belonging to these different categories. Click the tab above to switch between different setting items and their details.






Click the Delete Item icon Delete Item to delete the specific device item.

Note that only an offline device can be deleted. When a deleted device is registered to DMS once again in the future, it will be shown in ungrouped list.

Click MOVE to show group selection window and move the device to the specific group.

Click **CLOSE** to leave the view window.



(2) Send Command to Device

Figure 46 Send commands to a device



Choose an ungrouped device from the list and click the send commands icon in the toolbar to send commands to a selected device. You can also right click a device from the list to show the **Send Command** option.

The supported commands include power on/off and reboot.

When devices are in some status, a command may not be active. Please refer to table 2 for more device type and active command details.

### (3) Move Devices to a Group




Figure 47 Move devices to a group  $_{68}$ 



Choose one or many devices in the list and click the move device icon in the toolbar to move selected devices to a specific group. When you choose multiple devices, please make sure they are belonged to the same device type.

You can also right-click a device from the list to show the Move to option.

Only groups available for a specific device type will be displayed in the group list. When the selected devices are in offline state, they will be applied with the new group setting after turning on.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click MOVE to move the devices to a specific group.

Click **CANCEL** or icon to restore your previous settings and leave the page.

#### DMS\_Administrator • Grouped Ungrouped Support 4 B 3 B 0 A & D Source Q. (52) MAC Address Online Time(GMT+08:00) e3a9d5l3c... E1;FD:1F:00:60:9F endpoint-0320... Bilby 103.9.244.147 20.1.3 SW U\_ 2024.04.23 00:09... 2db845aaf... 9C:71:A3:15:9E:57 endpoint-0320... 29BAC00 B4.1.199.25 2024.04.23 00:01... 77:EC:48:95:AD:AC endpoint-0320... 33.2.235.111 44841a1e0... 63:18:10:56:83:3E 160.10.34.212 22.8.3 2024.04.23 00:10... Send Command Move to DB:BE:19:DB:6F:2F 179.4.182.95 19.7.2 Default f2520d174.... B3:08:B0:C7:0F:BB C00 39.14.135.161 21.4,5 2024.04.23 00:14... Facto... 0 View A7:3D:2F:6D:68:A3 90.13.78.146 1.6.13 Facto... 2024.04.23 00:13... 81eecad6cf.... Delete 3dca26175... 3B:5D:3C:EC:90:2C 29BXC00 200.8.241.251 22.2.2 Facto... 2024.04.23 00:08... endpoint-0320... ø e4bel4d6fc... 29:82:82:92:87:0A endpoint-0320... 201.6.66.205 20.12.1 Facto... 2024.04.23 00:06...

# (4) Delete Device

Figure 48 Delete Device

Choose one or many devices from the list and click the delete icon in the toolbar to delete the selected devices. **Note** that you can only delete devices which are in offline



state. When a deleted device is registered to DMS once again in the future, it will be shown in ungrouped list.

You can also right-click a device from the list to show the **Delete** option.

# 

# (5) Import Device

Figure 49 Import device to ungrouped

In Ungrouped main window, click the import icon in the toolbar to import device data. You can drag the file here or click **Browse** and choose the file (\*.zip) you want to import. You can only import one file at a time.



Click **IMPORT** to import device data and then leave the window. If there is any error happening during importing process, it shows error message. You can download and view the error report.

Click **CANCEL** or icon to leave the import window without changes.

# (6) Export Device Inventory Report




Figure 50 Export Device Inventory Report - Ungrouped

Click the export icon in the toolbar to export device inventory report. This will export information of all devices in the ungrouped page. The exported format is a .csv file with a file name DeviceList\_yyyymmdd\_hhmmss.csv ("DMS\_DeviceList": fixed characters, "yyyymmdd": exported year/month/day, "hhmmss": exported time - hour/minute/second).

Depending on your browser setting, the inventory report would be exported to a default file download location, or you would be asked to select a file location to save the file. If the is an error happened in exporting process, an error message



# (7) Redistribute Device




Figure 51 Redistribute Device

In Ungrouped page, you can click the redistribute icon in the toolbar to redistribute ungrouped devices based on export information of grouped devices. To restore the grouped data associated with devices, you must export device report in Grouped page in advance. Once imported, the system will distribute ungrouped devices into each group, based on the grouped data in the previous exported report.

You can drag the file or click the **Browse** button to select the file (\*.csv) and import. Only one file can be imported at a time.

After selecting the files to be imported, click the **REDISTRIBUTE** button to redistribute devices and leave the screen. If an error occurs during the distribution process, an error message will be displayed, and you can choose to download and view the error report.

Click **CANCEL** to leave the window without changes.



### 3.5.3 Support

Administrators can view online and VNC/SSH-supported devices, use VNC session to control and manage the remote desktop or use SSH to conduct remote connection, and furthermore clarify preliminary issues and fix problems for the connected devices.




Figure 52 Support Screen

Click sub-page **Support** in Device page. The list shows all online and VNC/SSH-supported device information, including each device's device name, device type, support type, and the last online time. The list defaults to the descending order of "Online Time", and the last online item will be displayed


first.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria to find particular data in support screen. After choosing the criteria (e.g. Device Type, MAC Address, IP, SN, SW Version, BIOS Version and Status) you want to use




and entering your search words, click the add rule icon \_\_\_\_\_\_ to add rule in search list. You can add one or several search criteria. After completing the setting, click SEARCH to start data searching; or click CANCEL to close search screen.




Click each column header to sort the data in order of letter or number.





Sort data in ascending order



# Figure 53 View Support Setting

Choose a device in the VNC- or SSH-supported device list to show device connection information, including device name, device type, MAC address, IP address, VNC port, SSH port, and SSH connection account of the device you want to connect to. This screen is read only.



Click icon to leave the device support setting page.




Figure 54 VNC connection succeeded

Click the VNC icon on the toolbar. The remote desktop is displayed after the connection is successful. The upper left corner of the window displays the name of the currently connected device and the connection type information.

Click **Disconnect** button to disconnect VNC connection and close the window.






Figure 55 VNC connection failed

If VNC connection fails, it will show connection failure message in the upper right corner of the window, e.g. Failed to connect to server (Disconnected).

Click Close Window button to close VNC connection window.





Figure 56 SSH connection succeeded

Click the SSH icon on the toolbar. The remote desktop is displayed after the connection is successful. The upper left corner of the window displays the name of the currently connected device and the connection type information.

You are able to enter and perform commands in the window.

Click Close Window button to disconnect SSH connection and close the window.






Figure 57 SSH connection failed

If SSH connection fails, it will show connection failure message in the connection window, e.g. **Permission denied**, **please try again**.

Click Close Window button to close SSH connection window.

#### 3.6 Profile

The Profile page provides device and connection configuration information. It lets you manage and configure grouped devices and connection settings.

Advanced device settings can be reconfigured on each client device individually.

Modified settings may be different from configuration profile in the specific group. The settings on the client device will be synchronized with the profile, after next device reboot or receiving updated profile from DMS.



### 3.6.1 Device Profile




Figure 58 Device Profile

Click **Profile** in the left side of the screen. You will see information of the created device profiles, including device profile name, device type, time zone, group number, and the last edited time. The list defaults to the descending order of "Last Edited Time", and the last edited item will be displayed first.

You can view, add, edit, copy, or delete a device profile item.


If there is a scheduled task being executed, an icon will be displayed on the left. When the mouse is moved to the top, a prompt message "Task is running" will be displayed.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria to find particular data in device profile screen. After choosing the criteria (e.g. Device Type, Device Profile, Description, Used Group, Create User and Create Time) you want to use and entering your search words, click the add rule icon to



add rule in search list. You can add one or several search criteria. After completing the setting, click **SEARCH** to start data searching; or click **CANCEL** to close search screen.



Click the import icon in the toolbar to import the device profile.

Click the export icon in the toolbar to export device profile. If you didn't choose any device from the list, it exports all device profiles. If a specific device profile is selected, it exports the selected data.

Click each column header to sort the data in order of letter or number.



Choose a device profile from the list and click a toolbar icon at the top of the window to edit, view, delete, or copy a device profile.

- Click the edit icon in the toolbar to edit device profile configuration.
- Click the view icon in the toolbar or click the left mouse button twice to view device profile information.
- Click the delete icon in the toolbar to delete a device profile.
- Click the copy icon in the toolbar to copy a device profile.



Right-click a device profile from the list and it will show a shortcut list of editing, viewing, deleting, and copying device profile, which is the same as the icons in the toolbar.

You can choose one or more device profiles at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and applied group states.

## (1) Add Device Profile

Before adding a device profile, ensure Device Type data has been created and configured in DMS.

When a client device is registered to DMS server, it will upload device type it belongs to. You don't need to manually add the device type. If there isn't any device being registered in DMS, a message **No Device exist.** appears when adding a device profile.




Figure 59 Add Device Profile - Info

Click the ADD icon ——— in Device Profile page to create a new device



profile. In the configuration window, enter the device profile name, choose device type, and configure the rest of settings.

The window will show different configuration content according to the selected **Device Type**. Here uses device type "29B8C00" as the example.

Click **Info** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. If a device type has been established and existed in

DMS, it will be displayed in the field in sequence.

- Device Profile: You must configure the device profile name. The length of the name field is 20 characters. Space is not allowed in device profile name.
- Device Type: Select a device type from the drop-down list. This field must be configured. The drop-down list is generated when a device is registered to the DMS server or the model name passed through
   Anyware Trust Center.
- Description: Lets you enter the device profile description. The length of the description is 200 characters. This field is optional.
- Click Next > or the Password tab on the left to move to the next setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 60 Add Device Profile - Password

The Password setting window shows user and administrator account/password configuration content. Click **Password** or any tab on the left to switch the setting page at any time during the configuration process.

- User Account: When the device is powered on, it will automatically log in with this account. This field must be filled in. Space is not allowed in account field.
- User Password: Configure the user log-in password if it is required.
- Admin Account: Configure the administrator account to authorize access to advanced settings. This field must be filled in. Space is not allowed in account field.
- Admin Password: The device's advanced configuration is protected by a password. You have to configure the password to get access to advanced configuration. This field must be filled in. Space is not allowed in password field. The default password is *Administrator*. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon <sup>9</sup> to



- display the data in the password field; click the Hide Password icon  $^{\text{$\emptyset$}}$  to hide the data in the password field.
- Click Next > or the Power Management tab on the left to move to the next setting page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 61 Add Device Profile - Power Management

The Power Management setting window shows wake-on-LAN, power on after power loss, and power button function configuration content. Click **Power Management** or any tab on the left to switch the setting page at any time during the configuration process.



- Wake-on-LAN: Select Disable or Enable from the drop-down list to disable/enable WoLAN in power off state. This field must be configured.
- Power Button Function: Select Ignore, Sleep, Power-Off, or Session Disconnecting from the drop-down list. When set to Ignore, no action is taken regardless of whether the device is in a VDI session; when set to Sleep, the device enters sleep mode regardless of whether the device is in a VDI session; when set to Power-Off, the device is turned off regardless of whether the device is in a VDI session; when set to Session Disconnecting, if the device is in a VDI session, pressing power button would disconnect the session. This field must be configured.
- Click Next > or the Network Settings tab on the left to move to the next setting page.
- Click < Previous or the Password tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.







Figure 62 Add Device Profile - Network Settings

The Network Settings window shows wireless network configuration content. Click **Network Settings** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 Wireless: Select Disabled or Enabled from the drop-down list. This field must be configured. When Enabled is selected, configure SSID (wireless network name), encryption (options: Open, WEP-ASCII, WEP-HEX, WPA-PSK, and WPA2-PSK) and Key (password).





- Click Next > or the Security Settings tab on the left to move to the next setting page.
- Click < Previous or the Power Management tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 63 Add Device Profile - Security Settings

The Security Settings window shows SSH and VNC configuration content. Click **Security Settings** or any tab on the left to switch the setting page at any time during the configuration process.

- SSH: Select Disabled or Enabled from the drop-down list. This field must be configured.
- SSH Password: Enter SSH password when SSH is enabled. This field must be filled in. Space is not allowed in password field. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- VNC: Select Disabled or Enabled from the drop-down list. This field must be configured.



- VNC Password: Enter VNC password when VNC is enabled. This field must be filled in. Space is not allowed in password field. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- VNC Port: This is a read-only field. The port number is 5900.
- Click Next > or the Certificate Settings tab on the left to move to the next setting page.
- Click < Previous or the Network Settings tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 64 Add Device Profile - Certificate Settings

The Certificate Settings window shows connection certificate configuration content. The certificate file must have been uploaded and stored in the software. The certificate details can be managed and viewed in Settings -> File -> Certificate page. Click

Certificate Settings or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

Certificate 1: Select certificate file by clicking the Expand icon
 to expand
 and show the file list that you can choose from. Only one can be selected at a time.





Certificate 2: Select certificate file by clicking the Expand icon
 to expand
 and show the file list that you can choose from. Only one can be selected at a
 time.



- If a profile is applied to a group, a message This item is used by group. is displayed. Click the Expand icon to expand and show applied group list.
   Click the Leave icon to collapse the expanded group list.
- Click Next > or the Date/Time Settings tab on the left to move to the next setting page.
- Click < Previous or the Security Settings tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 65 Add Device Profile – Date/Time Settings

The Date/Time Settings window shows time zone, time format, and NTP configuration content. Click **Date/Time Settings** or any tab on the left to switch the setting page at any time during the configuration process.

- Time Zone: Select a time zone that the devices are located from the drop-down list. This field must be configured.
- Time Format: Select 12 or 24 hour from the drop-down list. This field must be configured.
- NTP: Select Disabled or Enabled from the drop-down list. This field must be configured.
- NTP Server: Enter NTP server address. This field must be configured.
- Click Next > or the Upload Logo & Configure Desktop tab on the left to move to the next setting page.



- Click < Previous or the Certificate Settings tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.





Figure 66 Add Device Profile – Upload Logo & Configure Desktop

The Upload Logo & Configure Desktop window allows you to configure wallpaper image, logo and enable/disable system information. Click **Upload Logo & Configure Desktop** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured

Wallpaper: choose the wallpaper image file that you want to upload. It allows
uploading a single image file. Click the icon to extend the wallpaper



preview screen on the right. If you haven't chosen a wallpaper image, the preview screen shows grey image.




Click the icon to show the file selection window. After confirming the selected wallpaper file, the image will display in wallpaper preview screen. The Wallpaper will show the selected file name. The file format, size, and/or limitation would be different, according the selected device type.

Please refer to the file limitation description in the preview screen. Click the icon to clear selected file. The file preview screen and Wallpaper will return to the unedited state. Click to close the extended file setting screen.

This filed is optional.

Logo: choose the company logo file that you want to upload. It allows uploading a single logo file. Click the icon to extend the logo preview screen on the right. If you haven't chosen a logo image, the preview screen shows grey image.





- Click the icon to show the file selection window. After confirming the selected logo file, the image will display in logo preview screen.

  The Logo will show the selected file name. The file format, size, and/or limitation would be different, according the selected device type. Please refer to the file limitation description in the preview screen. Click the icon selected file. The file preview screen and Logo will return to the unedited state.

  Click to close the extended file setting screen. This filed is optional.
- System Information: Select Disabled or Enabled from the drop-down list to confirm whether or not to show system information on UI. This field must be configured.
- Click Next > or the USB Permission tab on the left to move to the next setting page.
- Click < Previous or the Date/Time Settings tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 67 Add Device Profile – USB Permission

The USB Permission window allows you to configure USB permissions and authorize/unauthorize certain USB devices by Class (Device Class, Subclass, Protocol) or ID (Vendor ID, Product ID). The permission settings will be applied after the remote session is established. Click **USB Permission** or any tab on the left to switch the setting page at any time during the configuration process.


Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured

- USB Permission Rule: Displays the current number of USB
  permission rules. If there is no existing rule, it will display blank in the field;
  otherwise it will display the current quantity in the field. You can add maximum
  10 rules of authorized devices and 10 rules of unauthorized devices.
- Click the icon next to the number of USB permission rules to expand and display the current list of USB permission rules. The USB permission rules have fields such as authorization type and new conditions that can be set. You can use the drop-down menu to switch between Any, Authorized, and

Copyright© 2024 HP Inc. 97



Unauthorized devices. After clicking any item in the list, the selected item will be highlighted and displayed its USB permission rule details. To delete this rule,



When adding a new USB authorization entry, click the icon click the icon

and

select Authorized in Permision. Select one of the following in Add new:


- Class: The USB device is authorized by its device class, sub-class, and protocol information
- ID: The USB device is authorized by its vendor ID and product ID information

Click the ADD icon to add this new rule to the list on the

Copyright© 2024 HP Inc.



right.




When adding a new USB authorization entry, click the icon and select

Unauthorized in Permision. Select one of the following in Add new:

- Class: The USB device is unauthorized by its device class, subclass, and protocol information
- ID: The USB device is unauthorized by its vendor ID and product
   ID information

Click the ADD icon to add this new rule to the list on the right.




- Click < Previous or the Upload Logo & Configure Desktop tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.



 Click the Reset Form icon Figure 16 to reset the page content

back to the default state and the first setting page.

 Click CANCEL to restore your previous settings and leave the page.



(2) View Device Profile

Figure 68 View Device Profile - 1

Choose a device profile from the list and click the view icon in the toolbar or click the left mouse button twice to view device profile configuration information. You can also right-click a device profile from the list to show the **View** option.

CANCEL



The window will show different configuration content according to the selected **Device Type**. Here uses device type "29B8C00" as the example. Click **Info** or any tab on the left to switch the view page at any time during the process.

The window shows Info, Password, Power Management, Network, Security, Certificate, Date/Time Settings, Upload Logo & Configure Desktop, and USB Permission settings.

- If a profile is applied to a group, a message **This item is used by group.** is displayed. Click the Expand icon

  to expand and show applied group list. Click the Leave icon to collapse the expanded group list.
- Click Next > to move to the next setting page.
- Click < Previous to move back to the previous setting page.
- Click EDIT to enter device profile editing window.
- Click CANCEL to close the view page.
- Click the Delete Item icon Delete Item to delete the device profile

item. If the item was applied to a group, you are not allowed to delete

it.






Figure 69 View Device Profile - 2

If the viewed device profile is processing tasks, a message **This item is included in**processing tasks. is displayed. You can only view the processing task details but cannot edit or delete it.

If a profile is applied to a group, a message **This item is used by group.** is displayed. Click the Expand icon to expand and show applied group list.

Click the Leave icon to colla

to collapse the expanded group list.

- Click Next > to move to the next setting page.
- Click < Previous to move back to the previous setting page.</li>
- Click CANCEL to close the view page.

### (3) Edit Device Profile

You can only edit a device profile which is not performing a task. If a device profile is applied to one or more groups, and there is no group in performing a task, DMS will



display new task scheduling after completing device profile editing. Performing the task will apply the changed device profile to all devices in the group(s).




Figure 70 Edit Device Profile - Info

Choose a device profile from the list and click the edit icon in the toolbar to edit device profile configuration. You can also right-click a device profile from the list to show the **Edit** option.

The window will show different configuration content according to the selected **Device Type**. Here uses device type "29B8C00" as the example. Click **Info** or any tab on the left to switch the setting page at any time during the configuration process.

- Device Profile: You must configure the device profile name. The length of the name field is 20 characters. Space is not allowed in device profile name.
- Device Type: This field is read only and cannot be modified. The data source is generated when a device is registered to the DMS server or the model name passed through Anyware Trust Center.



- Description: Lets you enter the device profile description. The length of the description is 200 characters. This field is optional.
- Click Next > or the Password tab on the left to move to the next setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to restore your previous settings and leave the page.




Figure 71 Edit Device Profile - Password

The Password setting window shows user and administrator account/password configuration content. Click **Password** or any tab on the left to switch the setting page at any time during the configuration process.



- User Account: When the device is powered on, it will automatically log in with this account. This field must be filled in. Space is not allowed in account field.
- User Password: Configure the user log-in password if it is required. After clicking the field, you can edit the password and display the password icon.
   Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- Admin Account: Configure the administrator account to authorize access to advanced settings. This field must be filled in. Space is not allowed in account field.
- Admin Password: The device's advanced configuration is protected by a password. You have to configure the password to get access to advanced configuration. This field must be filled in. Space is not allowed in password field. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field: click the Hide
  - Password icon to hide the data in the password field.
- Click Next > or the Power Management tab on the left to move to the next setting page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 72 Edit Device Profile – Power Management

The Power Management setting window shows wake-on-LAN, power on after power loss, and power button function configuration content. Click **Power Management** or any tab on the left to switch the setting page at any time during the configuration process.

- Wake-on-LAN: Select Disable or Enable from the drop-down list to disable/enable WoLAN in power off state. This field must be configured.
- Power Button Function: Select Ignore, Sleep, Power-Off, or Session Disconnecting from the drop-down list. When set to Ignore, no action is taken regardless of whether the device is in a VDI session; when set to Sleep, the device enters sleep mode regardless of whether the device is in a VDI session; when set to Power-Off, the device is turned off regardless of whether the device is in a VDI session; when set to Session Disconnecting, if the device is in a VDI session, pressing power button would disconnect the session. This field must be configured.



- Click Next > or the Network Settings tab on the left to move to the next setting page.
- Click < Previous or the Password tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 73 Edit Device Profile - Network Settings


The Network Settings window shows wireless network configuration content. Click **Network Settings** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 Wireless: Select Disabled or Enabled from the drop-down list. This field must be configured.



- Click Next > or the Security Settings tab on the left to move to the next setting page.
- Click < Previous or the Power Management tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.



# Figure 74 Edit Device Profile – Security Settings

The Security Settings window shows SSH and VNC configuration content. Click **Security Settings** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 SSH: Select Disabled or Enabled from the drop-down list. This field must be configured.



- SSH Password: Enter SSH password when SSH is enabled. This field must be filled in. Space is not allowed in password field. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- VNC: Select Disabled or Enabled from the drop-down list. This field must be configured.
- VNC Password: Enter VNC password when VNC is enabled. This field must be filled in. Space is not allowed in password field. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- VNC Port: This field is read only and is fixed at 5900.
- Click Next > or the Certificate Settings tab on the left to move to the next setting page.
- Click < Previous or the Network Settings tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 75 Edit Device Profile – Certificate Settings

The Certificate Settings window shows connection certificate configuration content. The certificate file must have been uploaded and stored in the software. The certificate details can be managed and viewed in Settings -> File

-> Certificate page. If you've configured a certificate previously, the **Certificate Citrix** or **Certificate VMware** will show the previously configured file name. Click **Certificate Settings** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

Certificate 1: Select certificate file by clicking the Expand icon to expand and show the file list that you can choose from. Only one can be selected at a time.





 Certificate 2: Select certificate file by clicking the Expand icon expand and show the file list that you can choose from. Only one can be selected at a time.



- Click Next > or the Date/Time Settings tab on the left to move to the next setting page.
- Click < Previous or the Security Settings tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 76 Edit Device Profile – Date/Time Settings

The Date/Time Settings window shows time zone, time format, and NTP configuration content. Click **Date/Time Settings** or any tab on the left to switch the setting page at any time during the configuration process.

- Time Zone: Select a time zone that the devices are located from the drop-down list. This field must be configured.
- Time Format: Select 12 or 24 hour from the drop-down list. This field must be configured.
- NTP: Select Disabled or Enabled from the drop-down list. This field must be configured.
- NTP Server: Enter NTP server address. This field must be configured.
- Click Next > or the Upload Logo & Configure Desktop tab on the left to move to the next setting page.



- Click < Previous or the Certificate Settings tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 77 Edit Device Profile – Upload Logo & Configure Desktop
The Upload Logo & Configure Desktop window allows you to configure wallpaper image,
logo and enable/disable system information. Click Upload Logo & Configure Desktop or
any tab on the left to switch the setting page at any time during the configuration
process. If you've configured a wallpaper and/or logo image previously, the Wallpaper
and/or Logo will show the previously selected file name.



• Wallpaper: choose the wallpaper image file that you want to upload. It allows uploading a single image file. Click the icon \_\_\_\_\_\_ to extend the wallpaper preview screen on the right. If you've chosen a wallpaper file, the preview screen shows the previously selected image. If you haven't chosen a wallpaper image, the preview screen shows grey image.



- If you've chosen a wallpaper file and want to use a new wallpaper image, you can directly click the icon

  to change the image or click

  Clear to clear the previous setting and then click

  to configure a new image.
- Click the icon

  to show the file selection window. After

  confirming the selected wallpaper file, the image will display in
  wallpaper preview screen. The Wallpaper will show the selected file name. The
  file format, size, and/or limitation would be different, according the selected
  device type. Please refer to the file limitation description in the preview screen.

  Click the icon

  Clear

  to clear selected file. The file preview screen and

  Wallpaper will return to the unedited state. Click to close the extended file


This filed is optional.

setting screen.

Logo: choose the company logo file that you want to upload. It allows uploading a single logo file. Click the icon to extend the logo preview screen on the right. If you've chosen a logo file, the preview screen shows the previously



selected image. If you haven't chosen a logo image, the preview screen shows arey image.




- If you've chosen a logo file and want to use a new logo image, you can directly click the icon to change the image or click to clear the previous setting and then click to configure a new image.
- Click the icon Chaose to show the file selection window. After confirming the selected logo file, the image will display in logo preview screen. The Logo will show the selected file name. The file format, size, and/or limitation would be different, according the selected device type. Please refer to the file limitation description in the preview screen. Click the icon selected file. The file preview screen and Logo will return to the unedited state.
  Click file to close the extended file setting screen. This filed is optional.
- System Information: Select Disabled or Enabled from the drop-down list to confirm whether or not to show system information on UI. This field must be configured.
- Click < Previous or the Date/Time Settings tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content
   Copyright© 2024 HP Inc.



back to the default state and the first setting page.

• Click **CANCEL** to restore your previous settings and leave the page.




## Figure 78 Edit Device Profile – USB Permission

The USB Permission window allows you to configure USB permissions and authorize/unauthorize certain USB devices by Class (Device Class, Subclass, Protocol) or ID (Vendor ID, Product ID). The permission settings will be applied after the remote session is established. Click **USB Permission** or any tab on the left to switch the setting page at any time during the configuration process.

- USB Permission Rule: Displays the current number of USB
  permission rules. If there is no existing rule, it will display blank in the field;
  otherwise it will display the current quantity in the field. You can add maximum
   10 rules of authorized devices and 10 rules of unauthorized devices.
- Click the icon next to the number of USB permission rules to expand and display the current list of USB permission rules. The USB permission rules have fields such as authorization type and new conditions that can be set. You



can use the drop-down menu to switch between Any, Authorized, and
Unauthorized devices. After clicking any item in the list, the selected item will
be highlighted and displayed its USB permission rule details. To delete this rule,
click the icon



- When adding a new USB authorization entry, click the icon
   and select
   Authorized in Permision. Select one of the following in Add new:
  - Class: The USB device is authorized by its device class, sub-class, and protocol information
  - ID: The USB device is authorized by its vendor ID and product ID information

Click the ADD icon to add this new rule to the list on the right.





- When adding a new USB authorization entry, click the icon and select Unauthorized in Permision. Select one of the following in Add new:
  - Class: The USB device is unauthorized by its device class, subclass, and protocol information
  - ID: The USB device is unauthorized by its vendor ID and product
     ID information


Click the ADD icon to add this new rule to the list on the right.



- Click < Previous or the Upload Logo & Configure Desktop tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.

Copyright© 2024 HP Inc.





• Click **CANCEL** to restore your previous settings and leave the page.

## Figure 79 Task scheduling for an edited device profile

If a device profile is applied to one or more groups, and there is no group in performing a task, DMS will display new task scheduling after completing device profile editing. The task must be added and executed. Performing the task will apply the changed device profile to all devices in the group(s).

You can execute the task within 5 minutes or in the future by specifying the date and time. The date can only be configured as Today or Tomorrow. Once you complete the setting, click the **Apply** button to save the changes and close the window.

The new task is displayed in the Task list with a name format of sTask\_D9999 (9999 is a randomly generated sequence number). A task of changing device profile or connection profile cannot be edited or deleted.

#### (4) Delete Device Profile

You can only delete a device profile which is not assigned to any group. When a device profile is assigned to a group, you can only view the device profile information.






Figure 80 Delete Device Profile

Choose a device profile from the list and click the delete icon in the toolbar to delete the selected device profile. You can also right-click a device profile from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.



#### (5) Export Device Profile




Figure 81 Export Device Profile Confirmation Window

Choose one or multiple device profiles from the device profile list to export the data. Click the export icon in the toolbar or click **Export** from the shortcut list to export device profile data.

If you didn't click and choose any device profile from the list, it exports all device profile data; if you click and choose a specific device profile from the list, it exports the selected device profile data.

Click **CANCEL** to leave the export window without changes.
Click **EXPORT** to export device profile data. Depending on your browser setting, a window may appear for you to choose the export file location, or the file is exported directly to an assigned download location. If there is any error happening during exporting process, it shows error message.



["DMS":("Version":"2.2.0","CreateTime":"20180531112834"],"deviceTypeData":[{"items":[("abilityFlag":{"referenceArea":("timeZone":"005\_001"),"supportControl of the control ,"imgResolution":[],"abilitySupport":1,"valueLength":[6,32],"decryptShowValue":1,"fileSize":[],"values":{},"name":"User Password","allowSpaceInValue":0,"displayFlag":{},"name":"Power Management","displayOrder":2,"abilitySupport":1,"allowSpaceInValue":0,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"fieldType":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValue":1,"allowSpaceInValu yriag :1; name : Power Management , displayOrder :2; abilitysupport :1; settingerios :({ Imgreshotion :0; ImgresolutionMustedual :0; riedlyge :1; sile e::0,"displayOrder:2; valueType::1,"subFileArray":[],"defaultValue":2,"required":1,"key":"002\_002","colorFormat":0);{"imgltemOption":0,"imgResolutionMuin","value":3};["name":"30 min","value":6);["name":"45 min","value":7);["name":"1hr","value":8);["name":"3 min","value":9);["name":"5 hr","value":19);["name":"5 hr","value":19);["name":"5 hr","value":19);["name":"5 hr","value":10);["name":"5 hr","value":10);["name":10,"imame":10, ey":"003\_004","colorFormat":0},{"imgItemOption":0,"imgResolutionMustEqual":0,"fieldType":3,"allowMultipleValues":0,"adaptiveControl":0,"imgResolution":}],"mutualExclusion":0,"effect":[{"value":0,"effectField":[{"effect":2,"fillValue":"","key":"003\_008"},("effect":2,"fillValue":"),("effect":2,"fill ], "abilitySupport":1, "valueLength":[1,1], "decryptShowValue":0, "fileSize":[], "values":{"content":[{"name":"Open", "value":0}, {"name":"WEP-ASCII", "value":1}, {" "adaptiveControl":0,"imgResolution":[],"abilitySupport":1,"valueLength":[1,1],"decryptShowValue":0,"fileSize":[],"values":{"content":[["name":"Disable","valu imgResolution":[],"abilitySupport":1,"valueLength":[1,1],"decryptShowValue":0,"fileSize":[],"values":{"content":[{"name":"Disable","value":0},{"name":"Enable qual":0, "fieldType":0, "allowMultipleValues":0, "adaptiveControl":0, "imgResolution":[], "abilitySupport":1, "valueLength":[1,10], "decryptShowValue":0, "fileSize":[ rder":7,"valueType":0,"subFileArray":["crt","cer","der","p7b","p7c","pfx","p12","pem"],"defaultValue":"","required":1,"key":"004\_007","colorFormat":0],("in },{"name":"GMT-08:00","value":4},{"name":"GMT-07:00","value":5},{"name":"GMT-06:00","value":6},{"name":"GMT-05:00","value":7},{"name":"GMT-04:30", me":"GMT-14:00","value":3},"mutualExclusion":0,"effect":[],"contentType":0,"usingContentKey":""],"name":"TimeZone","allowSpaceInValue":0,"displayOn "mutualExclusion":0,"effect":1,"value":0,"effect":0,"fillValue":"","key":"005\_004"]]},"value":1,"effectfield":[{"effect":0,"fillValue":"","key":"005\_004"]]},"value":1,"effectfield":[{"effect":0,"fillValue":"","key":"005\_004"]]},"value":0,"fileSize":[0,10000],"values":[},"name":"Wallpaper","allowSpaceInValue":0,"displayOrder":1,"valueType":0,"subFileArray":["png"],"defaultValue":" ultValue":0,"required":1,"key":"006\_003","colorFormat":0}},"key":"006"},{"abilityFlag":{},"name":"Display","displayOrder":7,"abilitySupport":0,"settingFields": uitvalue :u, required :i, key : 000\_005 ; colorformat :0jj, key : 000\_j, daintyring :u, mand : 000, in the property : "", "key : "007\_007"], {"effect ::0, "fillValue":"", "key":"07\_008"], {"effect ::0, "fillValue":"", "key":"01, "fillValue":", "key":", "fillValue": y . 00 \_00 / 3/17 effect :0., "invalue . ', key . 00 \_00 3/17 effect :0., "invalue . ', key . 00 \_00 3/17 value . ', key . 00 \_00 3/17 effect :0., "fillValue":"", "key":"007\_005"), "effect :0., "fillValue":"", "key":"007\_007\_007"), "effect :1., "fillValue":"", "key":"007\_002"), "effect :1., "fillValue":"", "key":"007\_002"), "effect :1., "fillValue":"", "key":"007\_002"), "effect :1., "fillValue":"", "key":"007\_002"), "effect :1., "fillValue":"", "key":"007\_005"), "effect :1., "fillValue":"", 1050", "value":26}, {"name":"1600x1200", "value":27}, {"name":"1920x1200", "value":28}, {"name":"1920x1080", "value":29}, {"name":"2048x1536", "value":30}, {"name":"300x1200", "value":300x1200", "value "Rotate Right","value":1},("name":"Rotate Left","value":2},{"name":"Inverted","value":3}],"mutualExclusion":0,"effect":[],"contentType":0,"usingContentKey' ze":[],"values":{"content":[],"mutualExclusion":1,"effect":[],"contentType":1,"usingContentKey":"007\_002"},"name":"Secondary Display","allowSpaceInValue' 07\_004"},"name":"Secondary Screen Orientation","allowSpaceInValue":0,"displayOrder":8,"valueType":1,"subFileArray":[],"defaultValue":0,"required":1,"key",,("name":"30 min","value":6},("name":"45 min","value":7},("name":"1 hr","value":8},("name":"3 hr","value":9},("name":"5 hr","value":10}],"mutualExclusion orFormat":0},("img|temOption":0,"imgResolutionMustEqual":0,"fieldType":0,"allowMultipleValues":0,"adaptiveControl":0,"imgResolution":[],"abilitySupport": e":0,"displayOrder":4,"valueType":1,"subFileArray":[],"defaultValue":50,"required":1,"key":"008\_004","colorFormat":0},{"imgItemOption":0,"imgResolutionM ingResolutionMustEqual":0, "fieldType":0, "allowMultipleValues":0, "adaptiveControl":0, "imgResolution":[], "abilitySupport":1, "valueLength":[0,100], "decrypt", es":{},"name":"Microphone Volume","allowSpaceInValue":0,"displayOrder":2,"valueType":1,"subFileArray":[],"defaultValue":50,"required":1,"key":"009\_002"

# Figure 82 Export Device Profile Data

The exported format is a compressed file with a file name

DMS\_DeviceProfile\_yyyymmdd\_hhmmss.zip ("DMS\_DeviceProfile": fixed characters, "yyyymmdd": exported year/month/day, "hhmmss": exported time - hour/minute/second). The compressed file includes text files.

The item or data is displayed with quotation marks (""). Two values are separated with a comma (","). If not specified otherwise, please do not change exported contents, so as to avoid any importing error.



# (6) Import Device Profile




Figure 83 Import Device Profile

In Device Profile main window, click the import icon in the toolbar to import device profile data. You can drag the file here or click **Browse** and choose the file (\*.zip) you want to import. You can only import one file at a time.

Click **CANCEL** to leave the import window without changes.

Click **IMPORT** to import device profile data and then leave the window. If there is any error happening during importing process, it shows error message. You can download and view the error report.



#### (7) Copy Device Profile




Figure 84 Copy Device Profile

In Device Profile main window, select a device profile item that you want to copy and click the copy icon in the toolbar or click **Copy** from the shortcut list to copy device profile data.

The fields and settings on the screen are all copied from the source's device profile data.

You can edit these settings except "Device Type", which must be the same as the source's device type.

Click **COPY** to save data and leave the window. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.

Click the **Reset Form** icon **Figure 16** to reset the page content back to the default state.

Click **CANCEL** to leave the copy device profile window without changes.



#### 3.6.2 Connection Profile




Figure 85 Connection Profile

Click **Profile** in the left side of the screen. Then click **Connection Profile** page to show connection profile items.

The list shows all created connection profiles, including each connection profile's name, device type, group number, connection number, and the last edited time. The list defaults to the descending order of "Last Edited Time", and the last edited item will be displayed first.

You can view, add, edit, copy, or delete a connection profile.

If there is a scheduled profile task being executed, an icon will be displayed on the left, and when the mouse is moved to the top, a prompt message "Task is running" will be displayed.


In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.



Click the advanced search icon to show advanced search screen. You can define search criteria to find particular data in connection profile screen.

After choosing the criteria (e.g. Device Type, Connection Profile, Connection, Connection Type, Description, Used Group, Create User and Create Time) you want to use and <a href="mailto:entering your search words">entering your search words</a>, click the add rule icon

to add rule in search list. You can add one or several search criteria. After completing the setting, click **SEARCH** to start data searching; click **CANCEL** to close search screen and go back to connection profile screen.




Click the import icon in the toolbar to import the connection profile.

Click the export icon in the toolbar to export connection profile. If you didn't choose any connection profile from the list, it exports all connection profiles. If a specific connection profile is selected, it exports the selected data.

Click each column header to sort the data in order of letter or number.





Sort data in ascending order

or descending order

Choose a connection profile in the page and click a toolbar icon at the top of the window to edit, view, delete, or copy a connection profile.

- Click the edit icon in the toolbar to edit a connection profile configuration.
- Click the view icon
   in the toolbar to view connection profile information.
- Click the delete icon in the toolbar to delete a connection profile. Click the copy icon in the toolbar to copy a connection profile.
- Click the expand icon in the toolbar to expand and show applied connection profiles and the relating connection information.
- Click the collapse icon in the toolbar to collapse the expanded connection profile list and its relating connection information.

Right-click a connection profile from the list and it will show a shortcut of editing, viewing, deleting, or copying a connection profile, which is the same as the icons in the toolbar.

You can choose one or more connection profiles at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and applied group states.



#### (1) Add Connection Profile




Figure 86 Add Connection Profile - Profile Info

Click the ADD icon — in Connection Profile page to create a new connection profile.

The window will show different configuration content according to the selected **Device Type.** Here uses device type "29B8C00" as the example. Click **Profile Info** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. If a device type has been established and existed in DMS, it will be displayed in the field in sequence.

- Connection Profile: You must configure the connection profile name.
   The length of the name field is 20 characters.
- Device Type: Select a device type from the drop-down list. This field must be filled in. The drop-down list is generated when a device is registered to the DMS server or the model name passed through Anyware Trust Center.



- Description: Lets you enter the connection profile description. The length of the description is 200 characters. This field is optional.
- Click Next > or the Connection Info tab on the left to move to the next setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state.
- Click CANCEL to restore your previous settings and leave the page.




Figure 87 Add Connection Profile - Connection Info

When adding a connection profile, it is required to fill in the connection info. Click

Connection Info or any tab on the left to switch the setting page at any time during the configuration process.



- Connection Name: You must configure the connection name. The length of the name field is 20 characters.
- Connection Type: Select a connection type from the drop-down list VMware,
   Citrix, RDP, and PCoIP. The list shows different configuration content according to the selected device type. This field must be chosen.
- Kiosk Mode: Select Disabled or Enabled from the drop-down list to configure
   Kiosk mode. This field must be chosen.
- Auto Connect: Select Disabled or Enabled from the drop-down list to configure automatic connection. When Kiosk mode is enabled, this field is read only. This field must be chosen.
- Auto Reconnect After Disconnect: Select Disabled or Enabled from the dropdown list to configure automatic reconnection. When Kiosk mode is enabled, this field is read only. This field must be chosen.
- Reconnect After N Seconds: When selecting Enabled in field "Auto Reconnect
  After Disconnect", this setting appears for you to configure a value between 1
  and 3600 (seconds). This field must be configured.
- Click Next > or Basic tab on the left to move to the next setting page.
- Click < Previous or the Profile Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 88 Add Connection Profile – Basic (VMware)

When you choose **VMware** in Connection Info -> Connection Type, the Basic setting window allows you to configure basic connection information: authentication method, server address, domain, user name and password. Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

- Authentication: Choose Account and Password or Smart Card from the dropdown list.
- Server: Configure server address. This field must be filled in. Space is not allowed in server address field.
- Domain: Configure the server domain name when you choose Account and Password in Authentication. This field must be filled in.
   Space is not allowed in domain name.



- Username: When you choose Account and Password in Authentication, enter connection user name if you would like to configure this setting in advance.
- Password: When you choose Account and Password in Authentication, enter connection password if you would like to configure this setting in advance.
   After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- Click Next > or the Redirection tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 89 Add Connection Profile – Basic (Citrix)




When you choose **Citrix** in Connection Info -> Connection Type, the Basic setting window allows you to configure basic connection information. Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Authentication: Choose StoreFront, Web or Smart Card from the drop-down list.
- When you choose StoreFront in Authentication, these fields are displayed for you to configure: server, domain, username, password, store name, delivery controller, connection mode, and application

### name




 When you choose Web in Authentication, the field of URL is displayed for you to configure:



 When you choose Smart Card in Authentication, these fields are displayed for you to configure: server, store name, delivery controller, application name, smart card driver, and smart card removal action.





- Click **Next >** or the **Redirection** tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 90 Add Connection Profile – Basic (RDP)

When you choose RDP in Connection Info -> Connection Type, the Basic setting window allows you to configure basic connection information:

authentication method, server address, domain, user name, password, and NLA. Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

- Authentication: Choose Account and Password or Smart Card from the dropdown list.
- Server: Configure server address. This field must be filled in. Space is not allowed in server address field.
- Domain: Configure the server domain name when you choose Account and Password in Authentication. This field must be filled in. Space is not allowed in domain name.
- Port: Configure the port. This field must be filled in.



- Username: When you choose Account and Password in Authentication, enter connection user name if you would like to configure this setting in advance.
- Password: When you choose Account and Password in Authentication, enter connection password if you would like to configure this setting in advance. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- NLA (Network Level Authentication): Select RDP, TLS, or NLA from the dropdown list. When Smart Card is selected in Authentication, NLA will be forced as TLS.
- Click Next > or the Redirection tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 91 Add Connection Profile - Basic (PCoIP)

When you choose **Teradici PCoIP** in Connection Info -> Connection Type, the Basic setting window allows you to configure server address. Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

- Server: Configure server address. This field must be filled in. Space is not allowed in server address field.
- Domain: Configure the server domain name if you would like to set up an automatic connection.
- Username: Enter connection user name if you would like to set up an automatic connection.
- Password: Enter connection password if you would like to set up an automatic connection. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the



password field; click the Hide Password icon to hide the data in the password field.

- Click Next > or the Redirection tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.





Figure 92 Add Connection Profile - Redirection

When you choose **Teradici PCoIP** in Connection Info -> Connection Type, this page is not displayed. When you choose **VMware** in Connection Info -> Connection Type, the Redirection setting window allows you to configure webcam & audio recording and client drive device redirection.





When you choose **Citrix** or **RDP** in Connection Info -> Connection Type, the Redirection setting window allows you to configure webcam & smart card, client drive, and serial port device redirection.



- Click **Next >** or the **Advanced** tab on the left to move to the next setting page.
- Click < Previous or the Basic tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.







Figure 93 Add Connection Profile - Advanced

When you choose **VMware** in Connection Info -> Connection Type, the Advanced setting window allows you to configure advanced settings: protocol, preferences of unverifiable connection, in session toolbar, Ctrl+Alt+Del confirm dialog, and sharing folder. When Kiosk mode is enabled, in-session toolbar will be set as *Hide*, which can't be changed.




When you choose **Citrix** in Connection Info -> Connection Type, the Advanced setting window allows you to configure advanced settings: in session toolbar.






When you choose **RDP** in Connection Info -> Connection Type, the Advanced setting window allows you to configure advanced settings: remote application, auto reconnect, speed level, sound, encryption level, wallpaper, font smooth,

RemoteFX, window content, keyboard event, compression, and low bandwidth.



When you choose **Teradici PCoIP** in Connection Info -> Connection Type, the Advanced setting window allows you to configure preferences of unverifiable connection, PCoIP high performance client, and PCoIP codec indicator settings..



- Click < Previous or the Redirection tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 94 Add Connection Profile – RD Gateway (RDP)

When you choose **RDP** in Connection Info -> Connection Type, the RD Gateway setting allows you to configure your Remote Desktop Gateway server: domain, hostname, port, account name, and account password. Click **RD Gateway** or any tab on the left to switch the setting page at any time during the configuration process.

- RD Gateway Server: Choose Disabled or Enabled from the drop-down list.
- Domain: Configure the server domain name when you enable RD Gateway
   Server. This field must be filled in. Space is not allowed in domain name.



- Hostname: Configure server hostname. This field must be filled in.

  Space is not allowed in server address field.
- Port: Configure the port. This field is optional.
- Account Name: Enter the account name. This field must be filled in.
   Space is not allowed in account name.
- Account Password: Enter the account password. This field must be filled in.
   Space is not allowed in password. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- Click < Previous or the Advanced tab on the left to move back to the previous setting page.
- Click ADD to add the new connection profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.



# View Connection Profile Delete Item Profile Info Connection Profile Device Type 005\_ConnProfile 29B8C00 Description Test Description - Connection Profile : 5 Group Name (0) Connection No Group Data 10 Create Time Edit Time 2024.04.24 00:05 by 0006 2024.04.24 00:05 by 0006

#### (2) View Connection Profile

Figure 95 View Connection Profile - 1

CANCEL

Choose a connection profile from the list and click the view icon in the toolbar to view connection profile configuration information. You can also right click a connection profile from the list to show the **View** option.

The window will show different configuration content according to the selected **Device Type**. Here uses device type "29B8C00" as the example.

The window shows connection profile information, including connection profile name, device type, description, applied group number and list, connection number, added and edited date.

- If a connection profile is applied to a group, a message **This item is used by**group. is displayed. Click the Expand icon to expand and show applied group list. Click the Leave icon to collapse the expanded group list.
- Click EDIT to enter the connection profile editing window.
   Click CANCEL to close and return to connection profile window.
- Click the Delete Item icon Delete Item to delete the connection



profile item. If the item was applied to a group, you are not allowed to delete it.




Figure 96 View Connection Profile - 2

If the viewed connection profile is processing tasks, it will show **This item is included in processing tasks**. You can only view the processing task details but cannot edit or delete it.

If a profile is applied to a group, a message **This item is used by group.** is displayed. Click the Expand icon to expand and show applied group list.

Click the Leave icon to collapse the expanded group list.

Click CANCEL to close the view page.

### (3) Edit Connection Profile

You can only edit a connection profile which is not performing a task. If a connection profile is applied to one or more groups, and there is no group in performing a task, DMS will display the new task in Task window after adding or editing a connection data in a



connection profile. Performing the task will apply the changed connection profile to all devices in the group(s).




Figure 97 Edit Connection Profile

Choose a connection profile from the list and click the edit icon in the toolbar to edit connection profile configuration. You can also right-click a connection profile from the list to show the **Edit** option.

- Connection Profile: You must configure the connection profile name.
   The length of the name field is 20 characters.
- Device Type: This field is read only and cannot be modified.
   Description: Lets you enter the connection profile description. The length of the description is 200 characters. This field is optional.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content



- back to the unedited state.
- Click CANCEL to restore your previous settings and return to the connection profile window.

#### (4) Delete Connection Profile

You can only delete a connection profile which is not assigned to any group. When a connection profile is assigned to a group, you can only view the connection profile information.





Figure 98 Delete Connection Profile

Choose a connection profile from the list and click the delete icon in the toolbar to delete the selected connection profile. You can also right-click a connection profile from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.





#### (5) Connections in Connection Profile

Figure 99 Expand Connection Profile information

Choose a connection profile from the list. Double-click left mouse button or click the icon on the left to expand and show the connection profile list. Double click left mouse button again or click the icon on the left to collapse the expanded connection profile list.

Connection profile list shows the details of connection information in the profile, including each connection's type (e.g. VMware, Citrix, RDP, or Teradici PCoIP), corresponding connection name, server address, user name, domain name, and the last edited time.



Click the add icon in an expanded connection profile to add a new connection in the connection profile.

Choose a connection item in the list and click a toolbar icon at the top of the window to edit, view, delete, and copy data.

- Click the edit icon
   in the toolbar to edit connection data.
- Click the view icon in the toolbar or click the left mouse button twice to view connection data.
- Click the delete icon in the toolbar to delete connection data.
- Click the copy icon in the toolbar to copy connection data. When copying connection data, you can either generate a new connection profile or select an existing connection profile.

Right-click a connection item from the list and it will show a shortcut list of editing, viewing, deleting, or copying connection data, which is the same as the icons in the toolbar.



You can choose one or more connection items in a connection profile. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices and applied group states.






Figure 100 View Connection - Connection Info

Choose a connection item from the list and click the view icon in the toolbar or click the left mouse button twice to view connection configuration information. You can also right-click a connection item from the list to show the **View** option.

The window will show different configuration content according to the selected **Connection Type**. Here uses connection type "VMware" as the example.

The window shows profile information, including connection name, connection type, added and edited date.

- Click **Next >** or the **Basic** tab on the left to move to the next setting page.
- Click EDIT to enter the connection editing window.
- Click CANCEL to close and return to connection window.
- Click the Delete Item icon Delete Item to delete the connection item. If the item was applied to a group, at lease one connection must be retained.






Figure 101 View Connection - Basic

The window will show configuration content of basic settings.

- Click **Next >** or the **Redirection** tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click **EDIT** to enter the connection editing window.
- Click **CANCEL** to close and return to connection window.






Figure 102 View Connection - Redirection

The window will show configuration content of redirection settings.

- Click **Next >** or the **Advanced** tab on the left to move to the next setting page.
- Click < Previous or the Basic tab on the left to move back to the previous setting page.
- Click **EDIT** to enter the connection editing window.
- Click **CANCEL** to close and return to connection window.






Figure 103 View Connection - Advanced

The window will show configuration content of advanced settings.

- Click < Previous or the Redirection tab on the left to move back to the previous setting page.
- Click **EDIT** to enter the connection editing window.
- Click CANCEL to close and return to connection window.

it.






Figure 104 Edit Connection - Connection Info

Choose a connection item from the list and click the edit icon in the toolbar to edit connection configuration information. You can also right-click a connection item from the list to show the **Edit** option.

The window will show different configuration content according to the selected **Connection Type**. Here uses connection type "VMware" as the example.

Click **Connection Info** or any tab on the left to switch the setting page at any time during the configuration process.

- Connection Name: You must configure the connection name. The length of the name field is 20 characters.
- Connection Type: This field is read only and cannot be modified.



Kiosk Mode: Select Disabled or Enabled from the drop-down list to configure
 Kiosk mode. This field must be chosen.



Auto Connect: Select Disabled or Enabled from the drop-down list to configure automatic connection. This field must be chosen.

Auto Reconnect After Disconnect: Select Disabled or Enabled from the dropdown list to configure automatic reconnection. This field must be chosen.

- Reconnect After N Seconds: When selecting Enabled in field "Auto Reconnect
  After Disconnect", this setting appears for you to configure a value between 1
  and 3600 (seconds). This field must be configured. Click Next > or Basic tab
  on the left to move to the next setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to close the page and return to the connection profile window.




Figure 105 Edit Connection - Basic

Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.



Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Authentication: Select Account and Password or Smart Card from the dropdown list to configure authentication method.
- Server: Configure server address. This field must be filled in. Space is not allowed in server address.
- Domain: When selecting Account and Password in Authentication, this field
  appears for you to configure the server domain name. This field must be filled
  in. Space is not allowed in domain name. Username: When selecting Account
  and Password in Authentication, enter connection user name if you would like
  to configure this setting in advance.
- Password: When selecting Account and Password in Authentication, enter connection password if you would like to configure this setting in advance. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- Click Next > or the Redirection tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
  - Click the **Reset Form** icon **Figure 16** to reset the page content back to the unedited state.

Click **CANCEL** to restore your previous settings and leave the page.






Figure 106 Edit Connection - Redirection

Click **Redirection** or any tab on the left to switch the setting page at any time during the configuration process.

- Webcam & Audio Recording: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Client Drive: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Click Next > or the Advanced tab on the left to move to the next setting page.



- Click < **Previous** or the **Basic** tab on the left to move back to the previous setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 107 Edit Connection - Advanced

Click **Advanced** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 Protocol: Select VMware Blast, PCoIP, or Microsoft RDP from the drop-down list. This field must be configured.

Preferences of unverifiable connection: Select Allow, Warning, or Reject from the drop-down list. This field must be configured.



- In Session Toolbar: Select Hide or Show from the drop-down list. When Kiosk mode is enabled, in-session toolbar will be set as Hide, which can't be changed.
- Ctrl+Alt+Del Confirm Dialog: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Sharing Folder: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Click < Previous or the Redirection tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to restore your previous settings and leave the page.




Figure 108 Add Connection - Connection Info

Click the add icon in a expanded connection profile to create a new connection in this particular connection profile.



The window will show different configuration content according to the selected **Connection Type**. Here uses connection type "VMware" as the example.

Click **Profile Info** or any tab on the left to switch the setting page at any time during the configuration process.

- Connection Name: You must configure the connection name. The length of the name field is 20 characters.
- Connection Type: Select a connection type from the drop-down list VMware,
   Citrix, RDP, and Teradici PColP. Different options are available depending on
   the device type you select. This field must be chosen.
- Kiosk Mode: Select Disabled or Enabled from the drop-down list to configure
   Kiosk mode. This field must be chosen.
- Auto Connect: Select Disabled or Enabled from the drop-down list to configure automatic connection. When Kiosk mode is enabled, this field is read only. This field must be chosen.
- Auto Reconnect After Disconnect: Select Disabled or Enabled from the dropdown list to configure automatic reconnection. When Kiosk mode is enabled, this field is read only. This field must be chosen.
- Reconnect After N Seconds: When selecting Enabled in field "Auto Reconnect
  After Disconnect", this setting appears for you to configure a value between 1
  and 3600 (seconds). This field must be configured.
- Click **Next >** or the **Basic** tab on the left to move to the next setting page.



- Click **ADD** to add the new connection info and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 109 Add Connection - Basic

Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

- Authentication: Select Account and Password or Smart Card from the drop-down list to configure connection method.
- Server: Configure server address. This field must be filled in. Space is not allowed in server address.



- Domain: When selecting Account and Password in Authentication, this field appears
  for you to configure the server domain name. This field must be filled in. Space is not
  allowed in domain name. Username: When selecting Account and Password in
  Authentication, enter connection user name if you would like to configure this setting
  in advance.
- Password: When selecting Account and Password in Authentication, enter connection password if you would like to configure this setting in advance. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide
   Password icon to hide the data in the password field.
- Click Next > or the Redirection tab on the left to move to the next setting page.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new connection info and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.






Figure 110 Add Connection - Redirection

Click **Redirection** or any tab on the left to switch the setting page at any time during the configuration process.

- Webcam & Audio Recording: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Client Drive: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Click Next > or the Advanced tab on the left to move to the next setting page.
- Click < Previous or the Basic tab on the left to move back to the previous setting page.</li>
- Click ADD to add the new connection info and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state and the first setting page.



Add Connection Reset Form Connection Info Preferences of unverifiable connection Protocol Basic VMware Blast Allow Redirection Advanced Ctrl+Alt+Del Confirm Dialog In Session Toolbar Hide Disabled v Sharing Folder Enabled < Previous ADD CANCEL

Click CANCEL to restore your previous settings and leave the page.

Figure 111 Add Connection - Advanced

Click **Advanced** or any tab on the left to switch the setting page at any time during the configuration process.

- Protocol: Select VMware Blast, PCoIP, or Microsoft RDP from the drop-down list. This field must be configured.
- Preferences of unverifiable connection: Select Allow, Warning, or
   Reject from the drop-down list. This field must be configured.
- In Session Toolbar: Select Hide or Show from the drop-down list. When Kiosk mode is enabled, in-session toolbar will be set as Hide, which can't be changed.
- Ctrl+Alt+Del Confirm Dialog: Select Disabled or Enabled from the drop-down list. This field must be configured.
- Sharing Folder: Select Disabled or Enabled from the drop-down list. This field must be configured.



- Click < Previous or the Redirection tab on the left to move back to the previous setting page.
- Click ADD to add the new connection info and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.





Figure 112 Task scheduling for an added or edited connection

If a connection profile is applied to one or more groups, and there is no group in performing a task, DMS will display new task scheduling after adding or editing connection in connection profile. The task must be added and executed. Performing the task will apply the changed connection profile to all devices in the group(s).

You can execute the task within 5 minutes or in the future by specifying the date and time. The date can only be configured as Today or Tomorrow. Once you complete the setting, click the **Apply** button to save the changes and close the window.

The new task is displayed in the Task list with a name format of sTask\_C9999 (9999 is a randomly generated sequence number). A task of changing device profile or connection profile cannot be edited or deleted.





### (6) Export Connection Profile

Figure 113 Export Connection Profile Confirmation Window

Choose one or multiple connection profiles from the connection profile list to export the data. Click the export icon in the toolbar or click **Export** from the shortcut list to export connection profile data.

If you didn't click and choose any connection profile from the list, it exports all connection profile data; if you click and choose a specific connection profile from the list, it exports the selected connection profile data.

Click CANCEL to leave the export window without changes.

Click **EXPORT** to export connection profile data. Depending on your browser setting, a window may appear for you to choose the export file location, or the file is exported directly to an assigned download location. If there is any error happening during exporting process, it shows error message.

#### Device Management Software Administrators' Guide


# Figure 114 Export Connection Profile Data

The exported format is a compressed file with a file name

DMS\_ConnectionProfile\_yyyymmdd\_hhmmss.zip ("DMS\_ConnectionProfile": fixed characters, "yyyymmdd": exported year/month/day, "hhmmss": exported time – hour/minute/second). The compressed file includes text files.

The item or data is displayed with quotation marks (""). Two values are separated with a comma (","). If not specified otherwise, please do not change exported contents, so as to avoid any importing error.





## (7) Import Connection Profile

Figure 115 Import Connection Profile

In Connection Profile main window, click the import icon in the toolbar to import connection profile data. You can drag the file here or click **Browse** and choose the file (\*.zip) you want to import. You can only import one file at a time.

Click **CANCEL** or icon to leave the import window without changes.

Click **IMPORT** to import connection profile data and then leave the window. If there is any error happening during importing process, it shows error message.

You can download and view the error report.



### (8) Copy Connection Profile




Figure 116 Copy Connection Profile - Profile Info

In Connection Profile main window, select a connection profile item that you want to copy and click the copy icon in the toolbar or click **Copy** from the shortcut list to copy connection profile data.

The fields and settings on the screen are all copied from the source's connection profile data. You can then edit these settings.

Click **Next >** or the **Connection** tab on the left to move to the next setting page.

Click **COPY** to save data and leave the window. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.

Click the **Reset Form** icon **Figure 16** to reset the page content back to the default state.

Click CANCEL to leave the copy connection profile window without changes.





Figure 117 Copy Connection Profile - Connection

The page allows you to select the connection items you want to copy into connection profile. All items are copied by default, but you can edit them.

Click Deselect All to deselect all chosen items. Click Select All to choose all items.

Click < **Previous** or the **Profile Info** tab on the left to move back to the previous setting page.

Click **COPY** to save data and leave the window. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.

Click the Reset Form icon Figure 16 to reset the page content back to the default state.

Click **CANCEL** to leave the copy connection profile window without changes.



# (9) Copy Connection




Figure 118 Copy Connection – Create New Profile

If you select copying a connection item to a new connection profile, this window appears for you to configure connection profile details except **Device Type**, which must be the same as the source's device type.

The fields and settings on the screen are all copied from the source's connection data. You can then edit these settings.






Figure 119 Copy Connection – Select One Profile

If you select copying an existing connection profile, this window appears for you to select a connection profile from all connection profiles which have the same device type as the copy source.

The fields and settings on the screen are all copied from the source's connection data. You can then edit these settings.

#### 3.7 Task

The DMS can schedule the profile to be written to the devices. You can add, view, or delete a scheduling task. In Group or Profile window, any changes of device profile or connection profile will be shown in Task overview window. You can only view a changing profile task but cannot edit or delete the task.

When a task is executing, if a group receives more than one task at the same time, the executing order is based on the task creating time. If a task is created earlier, that task will be executed fist.






Figure 120 Task Overview

Click **Task** in the left side of the screen. You will see the overview of the created and configured tasks, including each task's name, executing command, executing frequency, starting time, due plan, and the specify condition.

The Task overview list is displayed according to the scheduling time. A task in processing or in the queue is shown on the top of the list. A finished task is shown next. An invalid task is shown last.

In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria (e.g. Task, Command, Frequency, Status, Start Time,


End Type, Device Type, Device Profile, Connection Profile, Group, MAC

Address, Create User and Create Time) to find particular data in task screen. After choosing the criteria you want to use and entering your search words, click the add rule

icon Add Rule to add rule in search list. You can add one or several search criteria.



After completing the setting, click **SEARCH** to start data searching; click **CANCEL** to close search screen and go back to task screen.



Click each column header to sort the data in order of letter or number.



Sort data in ascending order

Choose a task from the list and click a toolbar icon at the top of the window



to interrupt, edit, view, or delete the task.

- Click the edit icon in the toolbar to interrupt the task.
- Click the edit icon in the toolbar to edit the task.
- Click the view icon in the toolbar or click the left mouse button twice to view the task configuration.
- Click the delete icon in the toolbar to delete the task.

Right-click a task from the list to show a shortcut list of editing, viewing, and deleting a task, which is the same as the icons in the toolbar.



The status of a task is shown on the left side of each task name. When the mouse is moved above the icon, the prompt message of the task status will be displayed. The following marking indicates the task status:

Task Status	Marking
Valid but haven't executed task	None
Processing task	<b>&amp;</b>
Executed task	<b>②</b>
Overdue and not performed task	8
Invalid task	8

Table 3 Task status and marking

To execute a task, if the device is in power off mode, DMS will send a power on command to the device first and then perform the further task command. If the task is a power off command, the device remains in power off mode without any action.

If DMS cannot execute a task, an error message **Task service is error. Please reboot or check the service.** appears on the screen. You can click the execute task icon on the left side of the message to re-execute the task and see if the issue would be fixed. If the error still exists, make sure the current DMS operating state and confirm the server and service work fine.

#### 3.7.1. Add Task

Before adding a task, ensure Device Type and Group data has been created and configured in DMS.

When a client device is registered to DMS server, it will upload device type it belongs to.

You don't need to manually add the device type. If there isn't any device being registered in DMS, a message **No Device exist.** appears when adding a task.



Add Task

Info
Group
Condition
Start Time

ADD

Reset Form

Command
Fower On

Next >

Group can be created and configured in Device -> Grouped.

Figure 121 Add Task - Info

Click the ADD icon \_\_\_\_\_\_ in Task page to create a new task. Click **Info** or any tab on the left to switch the setting page at any time during the configuration process.

- Task Name: You must configure the task name. The length of the name field is 1-20 characters. Space is not allowed in task name.
- Command: Select a command from the drop-down list power on, power off, reboot, factory reset, SW update, connection profile update, device profile update, and BIOS update. This field must be chosen.
- Click Next > or the Group tab on the left to move to the next setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to



the default state and the first setting page.

Click CANCEL to cancel the changes and leave the page.




Figure 122 Add Task - Group

Click **Group** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The second step is to assign a group to perform the task. The upper right corner of the window shows the default device type, e.g. 29B8C00 You can choose a device type from the drop-down list. The group list below shows the groups being sorted by device type.

In search field , you can search any data that meets your group search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

You can choose one or multiple groups from the list. Then click NEXT



- > or the **Condition** tab on the left to enter the next setting page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.



Figure 123 Add Task - Condition

Click **Condition** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The third step is to set the executing frequency of the task. Set up frequency of task execution from the drop-down list – once, daily, weekly, or monthly. An expanded section of



time setting is shown according to the frequency option you select. All executing time can only be set a day after the configuration date.


This field must be chosen.

When **Once** is selected in Frequency, the task executes one time only.

When **Daily** is selected in Frequency, the expanded section shows frequency interval setting for you to set the number of days in which the task should be started. Select every 1 to 30 days to repeat the task. The default value is 1.




When **Weekly** is selected in Frequency, the expanded section shows frequency interval option. Select every 1 to 30 weeks to repeat the task. The default value is 1. Then select one or multiple weekdays to perform the task (The starting day of each week is Sunday).




When **Monthly** is selected in Frequency, the expanded section shows frequency interval option. Select every 1 to 30 months to repeat the task. The default value is 1. Then select a day from the calendar to perform the task.





Or you can select a day of a specific week in a month to perform the task (The starting day of each week is Sunday).



When the selected condition doesn't exist, the system will display an error message **The** selected condition does not exist. You can re-configure the schedule condition.

- Click **Next >** or the **Start Time** tab on the left to move to the next setting page.
- Click < Previous or the Group tab on the left to move back to the previous setting page.



- Click **ADD** to add the new task and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.




Figure 124 Add Task - Start Time

Click **Start Time** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **Once** is selected in Frequency, the Set Start Time page appears for you to configure the starting time of the task.

Start Date: Click the calendar icon to set a task starting date.

This field must be chosen.



Start Time: Click the clock icon to set a task starting time. This field must be chosen.

- Click < Previous or the Condition tab on the left to move back to the previous setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.




Figure 125 Add Task - End Time

Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.


If **Daily**, **Weekly** or **Monthly** is selected in Frequency, the Set End Time page appears for you to configure the ending time of the task.



- End Type: Select an ending type from the drop-down list **Specific Date**, **Repeat Times**, or **Never**. This field must be chosen.
- When Specific Date is selected in End Type, an expanded section appears on the right side of the page to configure the ending date



 When Repeat Times is selected in End Type, an expanded section appears on the right side of the page to configure the times of



- When **Never** is selected in End Type, the task will be executed without stopping.
- Click < Previous or the Start Time tab on the left to move back to the previous setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.






Figure 126 Add Task - SW

Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **SW Update** is selected in Command, this page appears for you to configure an OS or firmware file after completing the Assign Group configuration. The file list shows all available OS and firmware file information, including file name and description.

In search field search any data that meets your firmware search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the column header with **File Name** to sort the data in order of letter or number. The default setting is listed in ascending order.



Sort data in ascending order File Name OS\_29B8C00\_1.1.38\_20200204 OS\_29B8C00\_1.3.24\_20200824 OS\_29B8C00\_1.4.11\_20201016 OS\_29B8C00\_1.4.35\_20200730 Sort data in descending order File Name OS\_29B8C00\_1.6.49\_20200318 You can only select one file for SW update and cannot OS\_29B8C00\_1.4.35\_20200730 choose multiple files. OS\_29B8C00\_1.4.11\_20201016 Click **NEXT** > or the **Condition** tab on the left OS\_29B8C00\_1.3.24\_20200824 to enter the next setting page.

- Click < Previous or the Group tab on the left to move back to the previous setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.




Figure 127 Add Task - BIOS



Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **BIOS Update** is selected in Command, this page appears for you to configure a BIOS file after completing the Assign Group configuration. The file list shows all available BIOS file information, including file name and description.

In search field, you can search any data that meets your firmware search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted

Click the column header with **File Name** data in order of letter or number. The is listed in ascending order.

color above the list.

Sort data in ascending order



Sort data in descending order

You can only select one file for BIOS update and cannot choose multiple files.

- Click NEXT > or the Condition tab on the left to enter the next setting page.
- Click < Previous or the Group tab on the left to move back to the previous setting page.
- Click ADD to add the new task and leave the page. If a required field is not filled
  in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state and the first setting page.
- Click CANCEL to cancel the changes and leave the page.



### **3.7.2. View Task**




Figure 128 View Task - 1

Choose a task from the list and click the view icon in the toolbar to view task configuration information. You can also right-click a task from the list to show the **View** option.

Click any tab on the left, including info, group, file, condition, start time and end time, to switch the setting page at any time during the configuration process.

The window shows task information, including task name, command, executing frequency, applied group number, starting date and time, ending type, specify condition, added and edited date.

If the entire applied groups are deleted, a message **Some groups have been deleted.** is displayed.

- Click NEXT > to enter the next setting page.
- Click < Previous to move back to the previous setting page.</li>
- Click **EDIT** to enter the task editing window.



- Click CANCEL to close the view page.
- Click the **Delete Item** icon Delete Item to delete the task item.




Figure 129 View Task - 2

If the viewed task is in processing or the task is shown in Group or Profile window, indicating a device or connection profile change, a message **This item is included in**processing tasks. or **This item is created by DMS**. is displayed. You can only view the task details but cannot edit or delete it.

- Click NEXT > to enter the next setting page.
- Click < **Previous** to move back to the previous setting page.
- Click CANCEL to close the view page.



### 3.7.3. Edit Task




Figure 130 Edit Task - Info

Choose a task from the list and click the edit icon in the toolbar to edit task configuration. You can also right-click a task from the list to show the **Edit** option.

Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Task Name: You must configure the task name. The length of the name field is 1-20 characters. Space is not allowed in task name.
- Command: This field is read only and cannot be modified.
- Click Next > or the Group tab on the left to move to the next setting page.
- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to cancel the changes and leave the editing page.






Figure 131 Edit Task - Group

Click **Group** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The Device Type field is read only (e.g. ) and cannot be modified. The list below is the corresponding group data after filtering according to the device type.

In search field search any data that meets your group search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

- You can choose one or many groups from the list. Then click NEXT > or the tab
   Condition on the left to enter the next editing page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.



- Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state.
- Click **CANCEL** to restore your previous settings and leave the editing page.




Figure 132 Edit Task - Condition

Click **Condition** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The third step is to set the executing frequency of the task. The window shows the selected frequency setting and you can change the setting, if you like. The Frequency setting is a drop-down list with options once, daily, weekly, and monthly. An expanded section of time setting is shown according to the frequency option you select. All executing time can only be set a day after the configuration date. This field must be chosen.




When Once is selected in Frequency, the task executes one time only.


When **Daily** is selected in Frequency, the expanded section shows frequency interval setting for you to set the number of days in which the task should be started. Select every 1 to 30 days to repeat the task.



When **Weekly** is selected in Frequency, the expanded section shows frequency interval option. Select every 1 to 30 weeks to repeat the task. Then select one or multiple weekdays to perform the task (The starting day of each week is Sunday).




When **Monthly** is selected in Frequency, the expanded section shows frequency interval option. Select every 1 to 30 months to repeat the task. Then select a day from the calendar to perform the task.





Or you can select a day of a specific week in a month to perform the task (The starting day of each week is Sunday).



When the selected condition doesn't exist, the system will display an error message **The** selected condition does not exist. You can re-configure the schedule condition.

- Click Next > or the Start Time tab on the left to move to the next setting page.
- Click < Previous or the Group tab on the left to move back to the previous setting page.



- Click **Save** to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click CANCEL to cancel the changes and leave the page.




Figure 133 Edit Task - Start Time

Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **Once** was selected in Frequency, the Set Start Time page appears for you to configure the starting time of the task.

Start Date: Click the calendar icon to set a task starting date.

This field must be chosen.

Start Time: Click the clock icon to set a task starting time. This field must be chosen.



- Click < Previous or the Condition tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click **CANCEL** or icon to cancel the changes and leave the page.




Figure 134 Edit Task - End Time


Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **Daily**, **Weekly** or **Monthly** was selected in Frequency, the Set End Time page appears for you to configure the ending time of the task.


End Type: Select an ending type from the drop-down list - Specific Date, Repeat Times, or Never. This field must be chosen.



When Specific Date is selected in End Type, an expanded section appears on the right side of the page to configure the ending date



 When Repeat Times is selected in End Type, an expanded section appears on the right side of the page to configure the times of



- When **Never** is selected in End Type, the task will be executed without stopping.
- Click < Previous or the Start Time tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click CANCEL to cancel the changes and leave the editing page.






Figure 135 Edit Task - File

Click any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

If **SW Update** or **BIOS Update** is selected in Command, this page appears for you to configure a file after completing the Assign Group configuration. The firmware list shows all available file information for this device type, including file name and description.

In search field, you can search any data that meets your firmware search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the column header with **File Name** to sort the data in order of letter or number. The default setting is listed in ascending order.



### Sort data in ascending order

^	File Name
	OS_29B8C00_1.1.6_20200115
	OS_29B8C00_1.2.28_20200610
	0S_29B8C00_1.2.66_20200430
	0S_29B8C00_1.5.76_20200901

Sort data in descending order

You can only select one file for file update choose multiple files.

✓ File Name
 OS\_29B8C00\_1.9.1\_20200709
 OS\_29B8C00\_1.5.76\_20200901
 OS\_29B8C00\_1.2.66\_20200430
 OS\_29B8C00\_1.2.28\_20200610

and cannot

tab on the left

- Click NEXT > or the Condition to enter the next setting page.
- Click < Previous or the Group tab on the left to move back to the previous setting page.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click **CANCEL** to cancel the changes and leave the editing page. **3.7.4. Delete Task**

If a task is in processing or the task is shown in Group or Profile window, indicating a device or connection profile change, you cannot delete the task.






Figure 136 Delete Task

Choose a task from the list and click the delete icon in the toolbar to delete the selected task. You can also right-click a task from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.



## 3.7.5. Interrupt Task




Figure 137 Interrupt Task

Choose a proceeding task from the list and click the interrupt icon in the toolbar to stop the selected task. You can also right-click a proceeding task from the list to show the **Interrupt** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Interrupt** to confirm the interruption.

### 3.8 History

The History Overview screen shows major device management activities in the past. It includes adding, editing, or deleting records, as well as task executing results. Except showing on the history window, you can also export the history records as a file for archives.







Figure 138 History Overview

Click **History** in the left side of the screen to show the history overview window. You will see the history records of editing activities and task executed results by any DMS users.

The overview page shows history record information, including date/time, record type, executed result, and description. The list defaults to the descending order of "Time", and the latest data will be displayed first.

The overview list is sorted in order of date/time. The latest item is shown on the top of the list.

Click each column header to sort the data in order of letter or number.






Click the **Clear All** icon to clear all of the history records. The task items in Task window will be cleared up as well.

The History Overview shows all of the history records by default. If the record items go beyond the limit of rows allowed on the screen, a **Load More** icon


appears at the bottom of the list. Click it to show more history records. When all items are shown, the bottom icon will change to **Bottom of**List Bottom of List. Click the calendar icon

to apply a date filter, including all, today, yesterday, last 7 days, last 30 days, and custom range, on the history records. When choosing a custom range, you will need to choose the starting and ending dates.




The History All record types by default. Click the type filter icon to apply a record type filter, including all, device, profile, task, or settings, on the history records.





Click the advanced search icon to show advanced search screen. You can define search criteria (Start Time, End Time, Type, Result, etc.) to find particular data in history screen. After choosing the criteria you want to use and entering your search words, click the add rule icon add rule in search list. You can add one or several search criteria. After completing the setting, click **SEARCH** to start data searching; click **CANCEL** to close search screen and go back to history overview screen.



If having **Fail** in the task result, you can click the task name with underline marking in Description to show the task details. If the task was deleted, the task name doesn't have an underline for you to click and see detailed information.

If the Description text goes beyond the cell width, it shows more info icon on the right side. Click it to show the full text, including date/time, record type, executed activity, executed result, and description.



An activity failure of adding, editing, or deleting an item in DMS is not recorded in history.

# 3.8.1. Export History





Figure 139 Export History

Click the Export icon to show history export setting page.

Configure file format and history type, and then configure the time period. The supported file formats are PDF, Excel, and text. The supported history types are device, profile, settings, and task. You can choose one or several history types at the same time.

Then configure the date filter. Click the calendar icon on the From and To date to select a filter range.





After selecting the from/to date, click EXPORT to export history records.

Click **CANCEL** to cancel this action and return to history overview window. **3.8.2. Supported Export File Formats** 




Figure 140 Export history file format - PDF

If PDF is selected in File Format, it exports a .pdf format file.



The exported file includes several sections. The DMS version and copyright information is shown on the upper right corner of the page. The major section shows all exported history records, including date/time, record type, executed result, and description. The latest item is shown on the top of the list.

The exported date and time is shown on the bottom left corner of the page. The current page number and the total number of pages are shown on the bottom right corner of the page.




Figure 141 Export history file format - Excel

If **EXCEL** is selected in File Format, it exports an excel format file.

The exported file includes four columns: date/time, record type, executed result, and description. The latest item is shown on the top of the list.



```
"Time", "Type", "Result", "Description"
"2017.05.11 17:00", "Task", "Done", "1708 edited Test_InTask_Once."
"2017.05.11 16:59", "Task", "Done", "1708 edited Test_InTask_Once."
"2017.05.11 16:12", "Task", "Done", "1708 edited Test_InTask_Once."
"2017.05.11 16:12", "Task", "Done", "1708 edited Test_InTask_Once."
"2017.05.11 15:39", "Task", "Done", "1708 edited Test_InTask_Once."
"2017.05.11 15:39", "Task", "Done", "1708 added sTask_0_149448840000."
"2017.05.11 15:39", "Device / Grouped ","Done", "1708 edited Test_InTask_01_A7."
"2017.05.11 15:25", "Task", "Done", "1708 added sTask_0_1494488400000."
"2017.05.11 15:25", "Task", "Done", "1708 added sTask_0_149448780000."
"2017.05.11 15:25", "Task", "Successfully, "Test192_WS edited Test_InTask_01_A7."
"2017.05.11 19:48", "Successfully, "Test192_WS edited Test_InTask_01_A7."
"2017.05.11 18:31", "Task", "Successfully, "Test192_WS Reboot_0 implemented Successfully."
"2017.05.11 08:01", "Task", "Successfully, "Test192_WS Reboot_0 implemented Successfully."
"2017.05.11 04:01", "Task", "Successfully, "Test192_MS_Off implemented Successfully."
"2017.05.11 03:02", "Task", "Successfully, "Test192_MR3_Off implemented Successfully."
"2017.05.11 03:02", "Task", "Successfully, "Test192_MR3_Off implemented Successfully."
"2017.05.10 22:01", "Task", "Successfully, "Test192_MR3_Off implemented Successfully."
"2017.05.10 22:01", "Task", "Successfully, "Test192_MS_UpCon implemented Successfully."
"2017.05.10 18:38", "Successfully, "Test192_MS_UpCon implemented Successfully."
"2017.05.10 18:39", "Powice of Grouped ", "Done", "1708 edited Test_InGroup_48
```

Figure 142 Export history file format - Text

If **TEXT** is selected in File Format, it exports a text format file.

Each exported data is put within inverted commas "". A comma mark (,) separates two exported data.

The exported file includes four items of information: date/time, record type, executed result, and description. The latest item is shown on the top of the list.

### 3.9 Settings

The Settings page lets you configure and manage device firmware, connection certificate file, asset image, DMS user account, and server. Only administrators can configure the settings. The account and DMS setting are configured with defaulted values. You can change the settings depending on the actual circumstances.



# 3.9.1. File (1) BIOS/SW





Figure 143 Device BIOS/OS/Certificate Setting

Click **Settings** in the left side of the screen. The default window is on BIOS/OS setting page, which shows device file information, including BIOS, OS and Certificate.

The BIOS/SW page shows BIOS/SW list supported by LvOS devices and Trusted Zero
Client devices. The list will be retrieved again each time you enter the page and sorted in
descending order of "Last Edited Time". The last edited item will be displayed first.

DMS displays the list for all types of client devices by default. Administrators can click the
icon to select the displayed types, including: All, LvOS and Trusted Zero Client.



In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.



Click each column header to sort the data in order of letter or number.



Sort data in ascending order


Sort data in descending

Choose a file from the list and click a toolbar icon at the top of the window

to edit, view, or delete the file. For Trusted Zero Client, the files are sourced from Anyware Trust Center, so it can only obtain the list and cannot perform other actions such as editing, viewing, and deletion.

- Click the edit icon in the toolbar to edit the file data.
- Click the view icon in the toolbar or click the left mouse button twice to view the file information.
- Click the delete icon in the toolbar to delete the file.

  Right-click a file from the list to show a shortcut list of editing, viewing, and deleting a file, which is the same as the icons in the toolbar.



### A. Add BIOS/SW

Before adding a file, ensure Device Type data has been created and configured in DMS. Currently DMS only support BIOS and OS update for thin clients installed with LvOS operating system.






Figure 144 Add BIOS/SW

Click the ADD icon — in File setting page to create a new file item.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are several items which include file upload, file type, device type, file version, build date, and description. Only the fields file upload and description can be edited. Others are read-only fields.
- File (X): Select the file you would like to upload. You can select one or many files.

  Click the upload icon to show the file selection page.

  After confirming, this field shows the file name and file number (X). The upload file icon is changed to the view file icon Click the icon to expand and show the file list you want to upload. Click the leave icon to collapse the expanded file list. This field must be chosen.
- DMS will check the uploaded file name. The file name rule is: file type\_device type\_version\_build date. The File Type is BIOS or OS.
   The Device Type must exist in DMS beforehand. For instance:



29B8C00. **Version** only allows numbers (0-9) and periods (.). **Build Date** is an 8-digit number representing the date (yyyymmdd) of releasing the file. The date cannot be greater than the uploading date (no future date is allowed).

- DMS will check the uploaded file and automatically fill its relevant information in read-only fields, such as file type, device type, version, and build date.
- Description: Lets you enter the file description. The length of the description is
   200 characters. This field is optional.
- Click **ADD** to add the new file and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.

### B. View BIOS/SW




Figure 145 View BIOS/SW - 1

Choose a file from the list and click the view icon in the toolbar or click the left mouse button twice to view file configuration information. You can also right click a file from the list to show the **View** option.



The window shows file information, including file name and number (X), file type, device type, version, build date, description, created and edited time.

Click the expand icon to expand and show uploaded file list. Click the Leave icon to collapse the expanded file list.

Click EDIT to enter file editing page.

Click **CANCEL** to close the page and return to file overview window.

Click the **Delete Item** icon Delete Item to delete the file item.




Figure 146 View BIOS/SW - 2

If the viewing file was assigned in a task, a message **This item is used by task.** appears on the View File window. You can only view a scheduled file and its details but cannot edit or delete it.

Click **CANCEL** to leave the View File window.



### C. Edit BIOS/SW




Figure 147 Edit BIOS/SW


Choose a file from the list and click the edit icon in the toolbar to edit file configuration. You can also right-click a file from the list to show the **Edit** option. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are several items which include file upload, file type, device type, file version, build date, and description. Only the field **Description** can be edited. Others are read-only fields.
- Note: DMS version 2.3.0 and above only support firmware (OS) uploading feature. Due to the change of file format and verifying mechanism in newer DMS versions, you are not able to save older firmware files successfully, when the older files are edited and saved.
- Device Type: This field is read only and cannot be modified.
- File (X): This field is read only and cannot be modified. This field shows the file name and file number (X means the number). Click the view file icon expand and show the applied file list. Click the



Leave icon fine to collapse the expanded file list.

- File Type, device type, version and build date are read only and cannot be modified.
- Description: Lets you enter the file description. The length of the description is
   200 characters. This field is optional.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click CANCEL to cancel the changes and leave the editing page.



### D. Delete BIOS/SW


Figure 148 Delete BIOS/SW

Choose a file from the list and click the delete icon in the toolbar to delete the selected file. You can also right-click a file from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.

When a file updating task is processing on some devices, the file cannot be deleted. Copyright© 2024 HP Inc. 215





# (2) Certificate

069\_CertFile.pem

LR 069 U

Figure 149 Certificate Setting

29B\_3\_CA

2027.01.23 00:00

2024.04.25 01:09

Click **Settings** in the left side of the screen and then click **Certificate** page, which shows previously uploaded certificate information, including file name, issue to/by, expiration date, and the last edited time. The list defaults to the descending order of "Last Edited Time", and the last edited item will be displayed first.


In search field, you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria (e.g. Certificate File, Issue to, Issue by and Expiration Date) to find particular data in file setting screen. After choosing the criteria you want to use and

Add Rule search words, click the add rule icon
to add rule in search list. You can add one or several search

criteria. After completing the setting, click **SEARCH** to start data searching; click **CANCEL** to close search screen and go back to certificate setting screen.






Click each column header to sort the data in order of letter or number.



Choose a file from the list and click a toolbar icon at the top of the window



- Click the edit icon in the toolbar to edit the certificate.
- Click the view icon in the toolbar or click the left mouse button twice to view the certificate details.
- Click the extend icon in the toolbar to extend the certificate period.
- Click the delete icon in the toolbar to delete the certificate.

Right-click a file from the list to show a shortcut list of editing, viewing, extending, and deleting a certificate, which is the same as the icons in the toolbar.





A. Add Certificate




Figure 150 Add Certificate

Click the ADD icon — in Certificate setting page to create a new certificate item. Please fill out or choose from all fields marked by asterisk (\*).

These fields must be filled in or configured.

- In Info page, there are several items which include upload certificate file, issue to/by, expiration date, and description. Only the fields Upload Certificate File and Description can be edited. Others are read-only fields.
- Upload Certificate File: Select the certificate file you would like to upload. You can only select one file with file format .pem. If your certificate uses other format, you have to use openssl software or other software to transfer it to .pem before uploading. Click the upload icon to show the file selection page. After confirming, this field shows the file name. The upload file icon



changed to the view file icon . Click the icon to expand and show the file list you want to upload. Click the leave icon to collapse the expanded file list. This field must be chosen.

- DMS will check the uploading file format and content. If the certificate was
  expired or cannot interpret the certificate content, the upload will fail and show
  an error message. Also, an existing certificate cannot be uploaded again.
- DMS will check the uploaded file and automatically fill its relevant information in read-only fields, such as issue to, issue by, and expiration date.
- Description: Lets you enter the certificate description. The length of the description is 200 characters. This field is optional.
- Click ADD to add the new certificate file and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.



# **B.** View Certificate




Figure 151 View Certificate

Choose a file from the list and click the view icon in the toolbar or click the left mouse button twice to view certificate information. You can also right-click a file from the list to show the **View** option.

The window shows previously uploaded certificate information, including file name, issue to/by, expiration date, description, and the added/edited date.

Click the expand icon to expand and show uploaded certificate list. Click the Leave icon to collapse the expanded file list.

Click **EDIT** to enter file editing page.

Click CANCEL to close the page and return to file overview window.

Click the **Delete Item** icon Delete Item to delete the file item.



#### C. Edit Certificate




Figure 152 Edit Certificate


Choose a certificate from the list and click the edit icon in the toolbar to edit certificate configuration. You can also right-click a file from the list to show the **Edit** option. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are several items which include upload certificate file, issue to/by, expiration date, and description. Only the field
   Description can be edited. Others are read-only fields.
- Upload Certificate File: This field is read only and cannot be modified. This field shows the certificate name. Click the view file icon to expand and show the applied file list. Click the Leave icon to collapse the expanded file list.
- Issue To, Issue By, and Expiration Date are read only and cannot be modified.
- Description: Lets you enter the certificate description. The length of the description is 200 characters. This field is optional.
- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.

Copyright© 2024 HP Inc.



- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click CANCEL to cancel the changes and leave the editing page.



### D. Extend Certificate

Figure 153 Extend Certificate

Choose an expired certificate from the list and click the extend icon in the toolbar to extend certificate. You can also right-click the expired certificate from the list to show the **Extend** option. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are two display blocks: original file and extend file. The original file shows read-only fields: issue to, issue by, and expiration date.
- Upload Certificate File: In extend file, select the certificate file you would like to upload. You can only select one file with file format .pem. If your certificate uses other format, you have to use openssl software or other software to transfer it to .pem before uploading. Click the upload icon to show the file selection page. After confirming, this field shows the file name. The upload file icon is



changed to the view file icon . Click the icon to expand and show the file list you want to upload. Click the leave icon to collapse the expanded file list. This field must be chosen.

- DMS will check the uploading file format and content. If the certificate was
  expired or cannot interpret the certificate content, the upload will fail and show
  an error message. Also, if the extend certificate file doesn't match the original
  issuing unit and the issuer, the new certificate cannot be successfully
  uploaded.
- DMS will check the uploaded file and automatically fill its relevant information in read-only fields, such as issue to, issue by, and expiration date.
- Click EXTEND to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page back to the default state.
- Click **CANCEL** to cancel the changes and leave the extending page.



#### BMS\_Administrator ~ File Administrator Server BIOS/SW Certificate PB C E Sand Q. # Ŏ Last Edited 298 0 CA 043\_CertFile.peni LR 043 U 2023.10.25 00:00 2024.04.25 00:43 042\_CertFile.pem LR\_042\_U 2023.06,25 00:00 2024.04.25 00:42 Edit 041\_CertFile.pem LR\_041\_U 2025.10.30 00:00 2024.04.25 00:41 Extend 040\_CertFile.pem LR\_040\_U 2023.05.01 00:00 2024.04.25 00:40 29B\_2\_CA 2025.05.13 00:00 2024,04.25 00:39 039\_CertFile.pem LR\_039\_U (1) 038\_CertFile.pem LR\_038\_U 29B\_2\_CA 2024.04.04 00:00 2024.04.25 00:38 LR 037 U 29B 1 CA 2027.01.02 00:00 2024.04.25 00:37 037 CertFile.pem • 2024.04.25 00:36 036. CertFile.pem LR 036 U 29B 1 CA 2027.04.22 00:00 Settings

## E. Delete Certificate

Figure 154 Delete Certificate

29B\_2\_CA

2026.01.15 00:00

2024.04.25 00:35

Choose a file from the list and click the delete icon in the toolbar to delete the selected certificate. You can also right-click a file from the list to show the **Delete** option.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.

When a certificate is applied to a group, the file cannot be deleted.

035\_CertFile.pem

LR 035 U



#### 3.9.2. Administrator





Figure 155 Administrator Setting

Click **Settings** in the left side of the screen and move to **Administrator** page. It shows DMS user information.

The Administrator page shows established DMS user information, including user ID, access level, user name, department, job title, and phone extension. The list defaults to the descending order of "User ID". Data with smaller numbers, letters arranged in front or characters with fewer strokes will be displayed first.


In search field , you can search any data that meets your search criteria. The system compares your entry to the data in the current list and displays matching data with a highlighted color above the list.

Click the advanced search icon to show advanced search screen. You can define search criteria (e.g. Access Level, User ID, Name, Department, Title, Extension, Create User and Create Time) to find particular data in administrator setting screen. After choosing the criteria you want to use and entering your search words, click the add rule icon






completing the setting, click **SEARCH** to start data searching; or click **CANCEL** to close search screen and go back to administrator setting screen.



Click each column header to sort the data in order of letter or number.



Choose a user from the list and click a toolbar icon at the top of the window



- Click the edit icon in the toolbar to edit the user data.
- Click the view icon in the toolbar or click the left mouse button twice to view the user information.
- Click the delete icon in the toolbar to delete the user.

Right-click a user from the list to show a shortcut list of editing, viewing, and deleting a user, which is the same as the icons in the toolbar.





You can choose one or more users at the same time. The active functions (i.e. isn't grayed out) in the toolbar or the shortcut list are different in accordance with different choices.

# (1) Add Administrator




Figure 156 Add Administrator

Click the ADD icon \_\_\_\_\_ in Administrator setting page to create a new administrator account. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Access Level: Select an access level from the drop-down list Admin or Viewer.
   An Admin (Administrator) has the full authority to view, add, edit, and delete data. A Viewer only has partial authority to view data.
  - This field must be chosen.
- User ID: You must configure a user ID, which is identified as DMS log-in account name. The length of the name field is 4-20 characters.



Space is not allowed in user ID.

- Name: Configure the user name. The length of the field is 1-20 characters. This
  field must be filled in. Space is not allowed in user name.
- Department: Configure department information. This field is optional.
   Space is not allowed in department name.
- Title: Configure job title information. The length of the field is 20 characters. This field is optional. Space is not allowed in job title.
- Extension: Configure phone extension number. The length of the field is 20 characters. This field is optional. Space is not allowed in extension field.
- Password: Configure password, which is identified as DMS log-in password. The password must be at least 6 but no more than 16 characters in length. This field must be configured. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon. Click the Show
   Password icon to display the data in the password field; click the Hide

  Password icon to hide the data in the password field.
- If user information is imported from user account system LDAP, click the icon to expand and show LDAP account data. If account data is imported from LDAP, the User ID, Name, Department, Title, and Extension data are read only and cannot be modified.


**Note:** The field data must be set first before expanding LDAP data. After expanding LDAP data, click account item from the list or search the account you want to add with the criteria of **User ID**, **Name**, **Department**, **Title**, or

**Extension**. With search criteria of **Department** or **Title**, the list is shown in group. Click the group name will show staffs in that department or title. Click the icon to collapse the expanded account list.

**Note:** Configure **Directory Service** in **Settings** -> **Server** first, before importing account data from LDAP.



- Click ADD to add the account data and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- If the added account is imported from LDAP, only the user ID is required to log in DMS.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first page.
- Click **CANCEL** to close the page and return to administrator overview window.



# (2) View Administrator

Figure 157 View Administrator

Choose an administrator from the list and click the view icon in the toolbar or click the left mouse button twice to view user information. You can also right click an administrator from the list to show the **View** option.

If account data is imported from LDAP, a message **This account is created by LDAP**. is displayed on the screen.



The window shows administrator information, including access level, user ID, user name, department, job title, extension, created and edited time.

Click **EDIT** to enter administrator editing page.

Click **CANCEL** to close the page and return to administrator overview window.

Click the **Delete Item** icon Delete Item to delete the administrator item.






Figure 158 Edit Administrator

Choose an administrator from the list and click the edit icon in the toolbar to edit administrator data. You can also right-click an administrator from the list to show the **Edit** option. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

Access Level: Select an access level from the drop-down list - Admin or Viewer.
 An Admin (Administrator) has the full authority to view, add, edit, and delete data. A Viewer only has partial authority to view data.

This field must be chosen.




- User ID: The user ID data is read only and cannot be modified.
- Name: Configure the user name. The length of the field is 4-20 characters. This field must be filled in. Space is not allowed in user name.
- Department: Configure department information. This field is optional.
   Space is not allowed in department name.
- Title: Configure job title information. The length of the field is 20 characters. This field is optional. Space is not allowed in jab title.
- Extension: Configure phone extension number. The length of the field is 20 characters. This field is optional. Space is not allowed in extension field.
- Reset Password: Configure your password, which is identified as DMS log-in password. The password must be at least 6 but no more than 16 characters in length. This field must be configured. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon.
  Click the Show Password icon
  to display the data in the password field;
  click the Hide Password icon
  to hide the data in the password field.

Note: If account data is imported from LDAP, the User ID, Name, Department, Title, and Extension data are read only and cannot be modified. You can only configure Access Level.

- Click SAVE to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to cancel the changes and leave the editing page.





# (4) Delete Administrator

Figure 159 Delete Administrator

Choose an administrator from the list and click the delete icon in the toolbar to delete the selected administrator. You can also right-click an administrator from the list to show the **Delete** option.

The DMS has a default user account **administrator** for you to log in and configure settings.

There is at least one user with **Admin** access level to perform DMS management. The default user cannot be deleted.

If the deleted user stays in DMS, any further activity will force the user to log out and return to log in window.

A confirmation dialogue appears. Click **Cancel** to leave the window without changes or click **Delete** to confirm the deletion.



#### 3.9.3. Server




Figure 160 Server Overview

Click **Settings** in the left side of the screen and move to **Server** page. It shows DMS server information.

The Server page shows **Directory Service**, **Database**, **File Store Area**, **Anyware Trust Center** settings and server information. If you would like to integrate user account system LDAP, change database, or update file store area, click the **Edit** icon on the item that you would like to change to edit the settings. **Database** and **File Store Area** are included in DMS package by default. If you have no specific needs, you do not need to change any settings.

In the upper side of the screen, it shows the last edited date and time.

#### (1) Directory Service

The Directory Service page lets you configure directory service server settings. It supports Microsoft Active Directory and LDAP. The DMS log-in account can be integrated in user directory service account.






Figure 161 Edit LDAP settings

Click the Edit icon at the side of Directory Service to edit directory service settings.

Click **Info** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.



- Type: a drop-down menu for you to choose a directory service type, including LDAP and Microsoft Active Directory (Microsoft AD). This field must be chosen.

  The default setting is LDAP for you to configure LDAP relating settings.
- Base DN: The distinguished name of the search base object defines the location in the directory from which the directory service search begins. This field must be configured. Space is not allowed in base DN.
- Server Name: Configure server name, which is the location of directory service. This field must be filled in. Space is not allowed in server name.
- Port: Configure server port. This field must be filled in. Space is not allowed in port field.
- Login ID: Configure log-in ID, which is the LDAP user account. The account must have the authority to search LDAP data and LDAP search base. This field must be configured. Space is not allowed in login ID.
- Reset Password: Configure password, which is the LDAP user password. This field must be filled in. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon. Click the Show
   Password icon to display the data in the password field; click the Hide
   Password icon to hide the data in the password field.
- Append Base DN to User DN: The checkbox is checked by default, which saves
   User DN under Base DN. If User DN isn't located under Base DN, you can
   uncheck this field.
- Click Next > or the Search Filter tab on the left to move to the next setting page.
   Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to cancel the changes and leave the editing page.






Figure 162 Microsoft Active Directory settings - Info

Click the Edit icon by the side of Directory Service to edit directory service settings.

Click **Info** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Type: a drop-down menu for you to choose a directory service type, including LDAP and Microsoft Active Directory (Microsoft AD). This field must be chosen. The default setting is LDAP. Choose Microsoft Active Directory to configure Microsoft AD relating settings.
  - Base DN: The distinguished name of the search base object defines the location in the directory from which the directory service search begins. This field must be configured. Space is not allowed in base DN.
- Server Name: Configure server name, which is the location of directory service. This field must be filled in. Space is not allowed in server name.



•

- Port: Configure server port. This field must be filled in. Space is not allowed in port field.
- Login ID: Configure log-in ID, which is the Active Directory user account. The
  account must have the authority to search AD data and LDAP search base.
   This field must be configured. Space is not allowed in login ID.
- Reset Password: Configure password, which is the Active Directory user password. This field must be filled in. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon.
   Click the Show Password icon to display the data in the password field;
   click the Hide Password icon to hide the data in the password field.
- Domain: Configure the Active Directory domain name. This field must be filled in. Space is not allowed in domain name.
- Append Domain to Login ID: The checkbox is checked by default. When the field
  is checked, except login ID, AD login account will also include domain
  information, e.g. domain\Login ID. If you don't need to add domain information,
  you can uncheck this field.
- Click Next > or the Search Filter tab on the left to move to the next setting page.
   Click Save to save the changes and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to cancel the changes and leave the editing page.






Figure 163 Search Filter setting

The LDAP or Microsoft AD accounts may include some employees that have left your organization. When adding a DMS user account, you can use search filter to sift your data down to just the account information you need.

Click **Search Filter** or any tab on the left to switch the setting page at any time during the configuration process. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

The Search Filter is a text input field. You can enter your search conditions. This field is optional.

Click < **Previous** or the **Info** tab on the left to move back to the previous setting page.

Click SAVE to let DMS verify the revised connecting configurations. If the
connection is validated, it will save the changes and leave the editing page; if
the connection fails, it shows error message and stay in the editing window. If a
required field is not filled in, it will show an error message and move the cursor
to the unfilled field.



- •
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to cancel the changes and leave the editing page.




Figure 164 Mapping Directory Services setting

Click the Mapping icon by the side of Directory Service to edit mapping directory service settings. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 Base DN: The field is read only and cannot be modified. It shows the location in the directory which the search begins.

User ID: Configure user account, which is the DMS log-in account.

This field must be configured.

- Name: Configure user name. This field must be configured.
- Title: Configure job title information. This field is optional.
- Department: Configure department information. This field is optional.
- Extension: Configure phone extension number. This field is optional.



**Note:** After configuring the fields, DMS will verify whether the data is valid or not. If the data is valid, it shows the verified icon . If not, it shows the warning icon .

- Click **SAVE** to let DMS verify configuration in all fields of the page. The verified results are shown on the right side of each field. The verified mark represents the data exists. The warning mark represents the data doesn't exist. Once all fields are verified as valid, DMS will save the changes and leave the editing page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to close the page and return to server window.






Figure 165 Clear Mapping Directory Service Settings

After the directory services is edited, a dialogue appears asking you whether you want to clear mapping settings or not. Click **Cancel** to preserve data in the fields without clearing mapping settings. Click **Clear** to remove the mapping data.

# (2) Database

The Database Server page is the place where DMS stores data. You can configure the storage location at an internal place (default) or an external place.






Figure 166 Edit Database

Click the Edit icon by the side of Database to edit database settings, where stores DMS data. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Server Name: Configure server name, which is the location of the database.
   This field must be filled in. Space is not allowed in server name. DMS server default name is dms-01. If you would like to change the name, please do not enter localhost or 127.0.0.1 data.
- Database: Configure database name. This field must be filled in.
   Space is not allowed in database name.
- Port: Configure server port. This field must be filled in. Space is not allowed in port field.
- User Name: Configure user name, which is the database user account. This field must be configured. Space is not allowed in user name.
- Reset Password: Configure database user password. This field must be filled in.
   Space is not allowed in password. After clicking the field, you can edit the



password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.

- Click SAVE to save the changes. DMS will perform a connection examination to verify new settings. If the connection is successful, it saves the changes and leaves the editing page. If the connection is failed, it shows error message and stays in the editing page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to close the page and return to server window.

#### (3) File Store Area

The File Store Area is the place where DMS stores device files. You can configure the storage location at an internal place (default) or an external place.






Figure 167 Edit File Store Area

Click the Edit icon by the side of File Store Area to edit file server settings, including file server, FTP server, and TFTP server. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are several settings items which include server name, TFTP port, TFTP / FTP storage path (SW and BIOS), file directory location (SW and BIOS), login account and password.
- Server Name: Configure server name, which is the location of file server. This
  field must be filled in. Space is not allowed in server name. DMS server default
  name is dms-01. If you would like to change the name, please do not enter
  localhost or 127.0.0.1 data.
- TFTP Port: Configure TFTP port. This field must be filled in. Space is not allowed in port field.
- SW TFTP / FTP Path: Configure TFTP and FTP link. This field must be filled in.
   Space is not allowed in this field.
- SW HTTP URL: Configure file location. This field must be filled in.



Space is not allowed in file location.

- Account: Configure account, which is the file server user account. This field must be configured. Space is not allowed in user account.
- Reset Password: Configure file server user password. This field must be filled in. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon. Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password
- Click SAVE to save the changes. DMS will perform a connection examination to verify new settings. If the connection is successful, it saves the changes and leaves the editing page. If the connection is failed, it shows error message and stays in the editing page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click CANCEL to close the page.



# (4) Trust Center




Figure 168 Edit Anyware Trust Center Setting

Click the Edit icon by the side of Trust Center to edit Anyware

Trust Center settings, including server address, user name and password. Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- In Info page, there are several settings items which include the Trust
   Center FQDN, administrator's account and password.
- Trust Center FQDN: Configure the address that Trust Center is located. The
  prefix must be "api". For example, if the FQDN is api.example.com, please enter
  api.example.com or example.com (the system will automatically add the prefix).
  This field must be filled in.
  - Space is not allowed in FQDN field.
- Version: This field is read only and cannot be modified. It shows the current
   Trust Center version.



- User Name: Configure Trust Center account, which is the administrator account that can access to the Trust Center. This field must be configured.
   Space is not allowed in user account.
- Reset Password: Configure administrator's password that can access to the Trust Center. This field must be filled in. Space is not allowed in password. After clicking the field, you can edit the password and display the password icon.
   Click the Show Password icon to display the data in the password field; click the Hide Password icon to hide the data in the password field.
- Click SAVE to save the changes. DMS will perform a connection examination to verify new settings. If the connection is successful, it saves the changes and leaves the editing page. If the connection is failed, it shows error message and stays in the editing page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the unedited state.
- Click **CANCEL** to close the page.



# 

# (5) Server Information

Figure 169 Server Information

Click the View icon by the side of Server Information to view server usage information, including operating system, IP address, CPU usage, hard drive usage, installed memory size, and file storage size.

The two pie charts below show the current usage size / remaining size of "Memory" and "File Storage Area" respectively.

If files are not located at local side, the storage area shows "N/A" and it doesn't display any information in the pie chart below.

Click the close icon in the upper right corner to close and return to the main server settings screen.

#### 3.10 Custom Design Portal

You can customize the DMS screen here. Currently DMS provides configuration on changing company information, including DMS logo and company name.





Figure 170 Customized DMS Login Design

Open a web browser and then enter the IP address of the DMS Custom Design Portal. (https://<IP Address>/DMSWeb/CustomizePortal.jsp). You will see the log-in screen of the DMS front page. The IP address is the assigned IP of the DMS server and will be different according to actual environment.

The default log-in administrator username is "dmsAdm" and the password is "dmsAdm" (Make sure you use exactly the same uppercase and lowercase letters).



# 3.10.1. Company Information




Figure 171 Customize Company Information

After you successfully log in DMS custom design portal, it shows company information configuration screen. You can change company name and DMS logo. DMS will demonstrate the current settings.

- Name: Enter the company name. The length of the name field is 4-50 characters. This field must be filled in. Space is not allowed in name field.
- Logo: The current DMS logo is displayed. Click Change to replace the current logo with the new logo you choose.
- Copyright Notice is an input and optional field. If this field is not provided, the
  contents of the copyright notice will not be displayed on the "Copyright Notice
  and Software Description" screen. Only the version number and the software
  contents used by DMS will be displayed.
- Click Reset button to reset your configuration back to unedited state.
- Click Save Settings button to save the settings.



Click the sign out icon

to log out DMS custom



design portal.




Figure 172 Change Logo

You can change logo by clicking **Change** button on company information screen. Click the file icon to browse your computer files and choose a logo image. The width/height of the logo image is 90/60 pixels. You can also drag the image file to the displayed window.

- Click the icon
   to enlarge or diminish logo.
- Click **CONFIRM** to save the change and leave the editing page.
- Click CANCEL to close the window and go back to company information screen.

## 3.11 Manage Trusted Zero Client

DMS works closely with Trusted Trust Center. Through the same interface, you can easily manage and configure Trusted Zero Clients which have registered to the Anyware Trust Center.



**Note:** Configure **Trust Center** in **Settings** -> **Server** first to import and show correct device information, before any further configurations. There are two setting areas "**Device Profile**" and "**Connection Profile**".

#### 3.11.1. Add Device Profile




Figure 173 Add Trusted Zero Client Device Profile - Info

Click the ADD icon — in Device Profile page to create a new device profile. In the configuration window, enter the device profile name, choose device type, and configure the rest of settings.

The window will show different configuration content according to the selected

**Device Type**. Here uses the model name "Bilby" as the example. Click **Info** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. If a device type has been established and existed in DMS, it will be displayed in the field in sequence.



- Device Profile: You must configure the device profile name. The length of the name field is 20 characters. Space is not allowed in device profile name.
- Device Type: Select a device type from the drop-down list. This field must be configured. The drop-down list is generated when a device is registered to the DMS server or the model name passed through Anyware Trust Center.
- Description: Lets you enter the device profile description. The length of the description is 200 characters. This field is optional.
- Click Next > or the Time tab on the left to move to the next setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 174 Add Trusted Zero Client Device Profile - Time



The Time Settings window shows Network Time Protocol (NTP) configuration content.

Click **Time** or any tab on the left to switch the setting page at any time during the configuration process.

- NTP Enabled: Select True or False from the drop-down list to enable or disable
   NTP. This field must be configured.
- NTP Server: Configure NTP server location. When True is selected in NTP
   Enabled, this field must be filled in. Space is not allowed in server address. The
   length of the field is 128 characters.
- NTP Port: Configure NTP port. When True is selected in NTP Enabled, this field must be filled in. Space is not allowed. The value limit is between 1 and 65536.
- Query Interval: Configure interval between NTP queries. Select 1 minute, 5 minutes, 30 minutes, 1 hour, or 1 day from the drop-down list. When True is selected in NTP Enabled, this field must be selected.
- Time Zone: Configure time zone that the device is located. Select
   Africa/Abidjan, Africa/Accra, or other region from the drop-down list.

   When True is selected in NTP Enabled, this field must be selected.
- Display Format Date: Configure date format displayed on the device. Select 09/30/2022, Friday, September 30, 2022, Sep 30 Fri, or other format from the drop-down list. When True is selected in NTP Enabled, this field must be selected.
- Display Format Time: Configure time format displayed on the device. Select
   13:00, 01:00 PM, or other format from the drop-down list. When True is selected
   in NTP Enabled, this field must be selected.
- Click **Next >** or the **Logging** tab on the left to move to the next setting page.
- Click < Previous or the Info tab on the left to move back to the previous setting page.



- Click ADD to add the new device profile and leave the page. If a required field is
  not filled in, it will show an error message and move the cursor to the unfilled
  field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 175 Add Trusted Zero Client Device Profile - Logging

The Logging Settings window shows message level configuration content. Click **Logging** or any tab on the left to switch the setting page at any time during the configuration process.

- Log Level: Select Info, Error, Debug, or Critical from the drop-down list to configure logging level. This field must be configured.
- Click **Next >** or the **Localization** tab on the left to move to the next setting page.



- Click < Previous or the Time tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 176 Add Trusted Zero Client Device Profile - Localization

The Localization Settings window shows language and keyboard layout configuration content. Click **Localization** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

 Language: Configure English/United States, French/France, or other language from the drop-down list. The field must be selected.



- Keyboard Layout: Configure keyboard layout the device uses. Select English
   (US) or other layout from the drop-down list. The field must be selected.
- Click Next > or the Certificates tab on the left to move to the next setting page.
- Click < Previous or the Logging tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 177 Add Trusted Zero Client Device Profile - Certificates

The Certificates Settings window shows server and client certificates (.csr) for your configuration. The server certificate files must have been previously uploaded and stored. You can manage and view the certificate information in Settings -> File -> Certificate. Click **Certificates** or any tab on the left to switch the setting page at any time

during the configuration process. Copyright© 2024 HP Inc. 257



Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

- Operational Renew Before (day): Select 0.1-2.9 days from the drop-down menu to configure the number of days before the certificate expires to extend the certificate. The field must be configured. Space is not allowed.
- Server Certificate File: Add server certificates. Click the icon
   to expand the certificate editing field and view the certificate list. The expanded
   Certificate Type field is defaulted to "Server". Select the certificate file, enter certificate description in the Purpose field, select certificate type "Brokering" or "802.1x", and then click the ADD icon

to add the server certificate. The newly added certificate will add an additional item in the Certificate field and the certificate list on the right.

**Note:** If there is no information in the drop-down menu, please go to Settings -> File -> Certificate to upload certificates.



You can view certificate information in the certificate list. After clicking any item in the list, the certificate-related information will be displayed in the center of the screen. You can click the icon below the list to delete this certificate or click the icon in the center of the screen to return to the certificate editing.





- Click Next > or the USB Authorization tab on the left to move to the next setting page.
- Click < Previous or the Localization tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 178 Add Trusted Zero Client Device Profile - USB Authorization

The USB Authorization Settings window shows USB device permission configuration content. Click **USB Authorization** or any tab on the left to switch the setting page at any time during the configuration process.

- Authorization Enabled: Select True or False from the drop-down list to enable or disable USB authorization feature. This field must be configured.
- Devices: Display the number of authorized USB devices. If there is no configured item, the field is blank. Click the Expand icon to to show or add the authorized and unauthorized list. You can select Any, Authorized or Unauthorized from the drop-down list to show the selected USB device information. Click the Remove icon to to delete a specific item. Or click the Device List icon adding the next item.





To add authorized devices, select Authorized in Permission. Select Class or ID from the drop-down list of Add new. When Class is selected, fill in device class, subclass and protocol fields to configure USB device class. When ID is selected, fill in vendor ID and product ID fields to configure USB device ID. Click the Add icon
ADD to add this rule in authorized list on the right.



To add unauthorized devices, select Unauthorized in Permission. Select Class or ID from the drop-down list of Add new. When Class is selected, fill in device class, subclass and protocol fields to configure USB device class. When ID is selected, fill in vendor ID and product ID fields to configure USB device ID. Click the Add icon

ADD to add this rule in unauthorized list on the right.





- Click Next > or the USB Device Config tab on the left to move to the next setting page.
- Click < Previous or the Certificates tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 179 Add Trusted Zero Client Device Profile - USB Device Config

The USB Device Config Settings window shows USB device bridging configuration content. Click **USB Device Config** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

Devices: Display the number of bridging USB devices. If there is no configured item, the field is blank. Click the Expand icon to show or add the bridging list. After clicking an item in the list, the selected data will be highlighted, and the setting content of the USB device bridging method will be displayed in the middle of the screen. Click the

Remove icon to delete a specific item. Or click the Device

List icon to continue adding the next item.





 To add bridging devices, select Bridged, Local Terminated or Not Forwarded from the drop-down list of Bridging Type. Then use the Add new drop-down menu, and use the options Class and ID to configure the details. When Class is selected, fill in device class, subclass, and protocol fields to configure USB device class.



When ID is selected, fill in vendor ID and product ID fields to configure USB device ID. Click the Add icon to add this setting in the device list on the right.





- Click Next > or the Keyboard Settings tab on the left to move to the next setting page.
- Click < Previous or the USB Authorization tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.






Figure 180 Add Trusted Zero Client Device Profile – Keyboard Settings

The Keyboard Settings window shows keyboard behavior configuration content. Click **Keyboard Settings** or any tab on the left to switch the setting page at any time during the configuration process.

- Repeat Rate: After you press and hold down a key on the keyboard, the key
  starts repeating itself. The speed at which it repeats is the repeat speed, which
  can be fast or slow. Enter how many characters you want to repeat in a second.
  This field is optional. The value limit is between 1 and 100.
- Repeat Delay: When you press and hold a key on the keyboard, the key
  eventually repeats itself. The pause between pressing the key and when it
  starts repeating is the repeat delay. Enter the period in millisecond to adjust
  repeat delay, which can be quick or slow. This field is optional. The value limit is
  between 1 and 5000.



- Click **Next >** or the **Browser Config** tab on the left to move to the next setting page.
- Click < Previous or the USB Device Config tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 181 Add Trusted Zero Client Device Profile – Browser Config


The Browser Config window shows browser behavior configuration content. Click

Browser Config or any tab on the left to switch the setting page at any time during the configuration process.




Browser Config: shows the number of browser configuration. Click the Expand icon to show or add the browser configuration list. After clicking an item in the list, the selected data will be highlighted, and the setting content of the display will be displayed in the middle of the

screen. Click the Remove icon to delete a specific item. Or click the Device List icon to continue adding the next item.



To add a new browser setting, enter the domain that is allowed to be accessed from the device browser. Click the add icon to add this config item. It will also appear on the list of right side.



- Click **Next >** or the **Trust Config** tab on the left to move to the next setting page.
- Click < Previous or the Keyboard Settings tab on the left to move back to the previous setting page.



Click **ADD** to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.

- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 182 Add Trusted Zero Client Device Profile - Trust Config

The Trust Config window set the trust method between the devices and the Trust Center.

Click **Trust Config** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured.

State: Select a trust method from the drop-down list: Registered or Connected.
 This field must be filled in. The "Registered" option requires the device to be registered and connected to the Trust Center



at least once before it can be trusted. The "Connected" option requires the device to actively connect to the Trust Center before it can be trusted. When set to "Connected", "Time Out" also needs to be set. The connection timeout is calculated in seconds, and the value limit is between 1 and 86400.



- Version Policy Enable: Select True or False from the drop-down menu to configure whether the device should be updated to the specified firmware version before the deadline.
- Click < Previous or the Browser Config tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.

## 3.11.2. View / Edit / Delete / Export / Import / Copy Device Profile

Refer to session 3.6.1 for detailed configurations.



#### 3.11.3. Add Connection Profile




Figure 183 Add Device's Connection Profile - Profile Info

Click the ADD icon — in Connection Profile page to create a new connection profile. In the configuration window, enter the connection profile name, choose device type, and configure the rest of settings. If several device types have been created and exist in the system, the first device type will be displayed in sorted order.

The window will show different configuration content according to the selected **Device Type**. Here uses the model name "Bilby" as the example.

Click **Profile Info** or any tab on the left to switch the setting page at any time during the configuration process.

Please fill out or choose from all fields marked by asterisk (\*). These fields must be filled in or configured. If a device type has been established and existed in DMS, it will be displayed in the field in sequence.

Connection Profile: You must configure the connection profile name.
 The length of the name field is 20 characters.



- Device Type: Select a device type from the drop-down list. This field must be configured. The drop-down list is generated when a device is registered to the DMS server or the model name passed through Anyware Trust Center.
- Description: Lets you enter the connection profile description. The length of the description is 200 characters. This field is optional.
- Click Next > or the Connection Info tab on the left to move to the next setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click **CANCEL** to restore your previous settings and leave the page.




Figure 184 Add Device's Connection Profile - Connection Info
When you create a new connection profile, you will have to add a new connection info
item. The Connection Info Settings window shows connection configuration content.
Click Connection Info or any tab on the left to switch the setting page at any time during
the configuration process.



- Connection Name: You must configure the connection name. The length of the name field is 20 characters.
- Connection Type: Select a connection broker from the drop-down list. This field must be configured. The list would be different, according the selected device type.
- Click Next > or the Basic tab on the left to move to the next setting page.
- Click < Previous or the Profile Info tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.
- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.




Figure 185 Add Device's Connection Profile - Basic



When Connection Broker is selected in Connection Type, the Basic Settings window shows detailed connection configuration content. Click **Basic** or any tab on the left to switch the setting page at any time during the configuration process.

- Alias: Configure broker name. The length of the name field is 32 characters.
   This field is optional.
- Broker Connection Type: Select Direct Connection, View Connection server,
   PCoIP Connection Broker, AWS Workspaces, or Auto Detect from the drop-down list.
- Connection URI: Configure connecting address. This field must be configured.
   Space is not allowed.
- Resource Name: Automatically configure remote desktop or connection pool name.
- VCS Port: When Resource Name is configured, you have to enter port information. Space is not allowed.
- Auto Launch If One Desktop: Select True or False from the drop-down list to allow the desktop automatically connected when there is only one remote desktop being configured.
- Cert Check Mode: Select Never Connect Untrusted, Warn Before
   Connect Untrusted, or Do Not Verify from the drop-down list.
- Login Username Caching: Select True or False from the drop-down list to allow user name catching.
- Click < Previous or the Connection Info tab on the left to move back to the previous setting page.
- Click ADD to add the new device profile and leave the page. If a required field is not filled in, it will show an error message and move the cursor to the unfilled field.



- Click the Reset Form icon Figure 16 to reset the page content back to the default state and the first setting page.
- Click CANCEL to restore your previous settings and leave the page.

## 3.11.4. View / Edit / Delete / Export / Import / Copy Connection Profile

Refer to session 3.6.2 for detailed configurations.

## 4 Troubleshooting

Troubleshooting refers to solving problems related to the software that manages, monitors, maintains or configures devices. Here are some common issues you may encounter and steps to troubleshoot them:

#### 4.1 Connection Issues

- Check the connection: Ensure that the connection between the devices (or the trust center) and the management software is normal, including network connection, data transmission line, etc.
- Check the network settings: Ensure that the network settings of the devices
   (or the trust center) and the management software are consistent, including IP address, subnet mask, gateway, etc.

### 4.2 Error Massages and Logs

- View logs: Check the error messages and logs for any error or warning messages, which may provide clues about the problem.
- Interpret the error message: search for relevant resources or documents relating to the error messages to find the solution.



## 4.3 Collect DMS Logs

In addition to displaying the software operation history from the History, the abnormal records are stored in directory /dms/exe/tomcat9/logs on the DMS server. When unresolvable problems are encountered, the logs can be further collected and provided for further analysis.

How to collect DMS logs:

a. Use SSH to log in to the DMS host server: Use the host administrator account *dms-adm* and password *P@ssw0rd* (default) to log in to the DMS host.

Execute the following command: ssh

dms-adm@<DMS host IP>

```
C:\02_Data\_Temp>ssh dms-adm@192.168.3.9

dms-adm@192.168.3.9's password:
Welcome to Ubuntu 20.04.6 LTS (GNU/Linux 5.15.0-79-generic x86_64)

* Documentation: https://help.ubuntu.com

* Management: https://landscape.canonical.com

* Support: https://ubuntu.com/advantage

Your Hardware Enablement Stack (HWE) is supported until April 2025.
Last login: Wed Aug 30 15:22:23 2023 from 192.168.3.13

dms-adm@0MS-01: $
```

b. Move directory to /dms/exe/tomcat9/ with the following command: cd /dms/exe/tomcat9/

```
dms-adm@DMS-01: $ cd /dms/exe/tomcat9/
dms-adm@DMS-01:/dms/exe/tomcat9$ ls -1
total 8
drwxrwxr-x 4 tomcat tomcat 4096 Aug 30 16:32 logs
drwxrwxr-x 6 tomcat tomcat 4096 Aug 30 16:43 webapps
dms-adm@DMS-01:/dms/exe/tomcat9$
```

c. Compress the log files in the directory: Compress the files in the logs directory and place the files in /tmp directory with the following command: tar zcvf /tmp/dmslog.tar.gz logs



```
dms-adm@DMS-01:/dms/exe/tomcat9$ tar zcvf /tmp/dmslog.tar.gz logs logs/
logs/sharelogs/
logs/sharelogs/DMSWeb.log
logs/sharelogs/DMSSrv.log
logs/sharelogs/DMSWeb.log.2023-08-25-1.gz
logs/sharelogs/DMSSry.log.2023-08-25-1.gz
logs/sharelogs/DMSSry.log.2023-08-25-1.gz
logs/stdOutDMSSrv.log.2023-08-25-1.gz
logs/stdOutDMSSrv.log
logs/stdOutDMSSrv.log
dms-adm@DMS-01:/dms/exe/tomcat9$
```

d. Log out of the DMS host: execute the following command to log out:

exit

```
dms-adm@DMS-01:/dms/exe/tomcat9/logs/sharelogs$ exit
logout
Connection to 192.168.3.9 closed.
C:\02_Data\_Temp>
```

e. Retrieve compressed files: Use sftp to download the files to your local machine with the following command:

```
sftp dms-adm@<DMS host IP>  # Connect to DMS host get
/tmp/dmslog.tar.gz  # Download compressed file bye  #
```

```
C:\02_Data\_Temp>sftp dms-adm@192.168.3.9

dms-adm@192.168.3.9's password:

Connected to 192.168.3.9.

sftp> get /tmp/dmslog.tar.gz

Fetching /tmp/dmslog.tar.gz to dmslog.tar.gz

/tmp/dmslog.tar.gz to dmslog.tar.gz

sftp> bye

C:\02_Data\_Temp>
```

### 4.4 Security Issues

Break the connection

- Enhance security: Ensure that the security settings of the software host can protect sensitive data, such as setting appropriate access rights and encryption measures.
- Updates and patches: Ensure that DMS software and device software is up to date and that security patches are applied in a timely manner.



# 4.5 Backup and Recovery

- Perform regular backups: Ensure regular backups of data and software settings to prevent data loss or system failure.
- Verify the recovery process: Verify the recovery process regularly to ensure rapid recovery in disaster situations.